



Euca2ools 3.4.1 Reference Guide

2020-12-03 Copyright for portions of this documentation are held
by Ent. Services Development Corporation LP, 2017. All other
copyright for this documentation is held by Eucalyptus Cloud, 2018

Contents

Euca2ools Overview.....	8
Overview of Euca2ools.....	8
Installing Euca2ools.....	8
Installing Euca2ools on RHEL / CentOS.....	8
Installing Euca2ools on Mac OS X.....	8
Configuring Euca2ools.....	9
Setting Environment Variables.....	9
Order of Precedence for Common Parameters.....	10
Working with Euca2ools Configuration Files.....	10
 EC2-Compatible Commands.....	 16
euca-allocate-address.....	16
euca-associate-address.....	17
euca-attach-volume.....	18
euca-authorize.....	19
euca-bundle-image.....	21
euca-bundle-instance.....	23
euca-bundle-and-upload-image.....	24
euca-bundle-vol.....	26
euca-cancel-bundle-task.....	29
euca-cancel-conversion-task.....	30
euca-create-group.....	31
euca-create-image.....	32
euca-create-keypair.....	34
euca-create-snapshot.....	35
euca-create-tags.....	36
euca-create-volume.....	37
euca-delete-bundle.....	39
euca-delete-disk-image.....	40
euca-delete-group.....	41
euca-delete-keypair.....	42
euca-delete-snapshot.....	43
euca-delete-tags.....	44
euca-delete-volume.....	45
euca-deregister.....	46
euca-describe-addresses.....	47
euca-describe-availability-zones.....	48
euca-describe-bundle-tasks.....	50
euca-describe-conversion-tasks.....	52
euca-describe-group.....	53
euca-describe-image-attribute.....	55
euca-describe-images.....	56
euca-describe-instance-status.....	59
euca-describe-instance-types.....	61
euca-describe-instances.....	63
euca-describe-keypairs.....	68
euca-describe-regions.....	69
euca-describe-snapshots.....	71

euca-describe-tags.....	73
euca-describe-volumes.....	75
euca-detach-volume.....	77
euca-disassociate-address.....	78
euca-download-bundle.....	79
euca-download-and-unbundle.....	80
euca-fingerprint-key.....	81
euca-get-console-output.....	82
euca-get-password.....	83
euca-get-password-data.....	84
euca-import-keypair.....	85
euca-import-instance.....	86
euca-install-image.....	89
euca-modify-image-attribute.....	91
euca-modify-instance-attribute.....	92
euca-modify-instance-type.....	94
euca-monitor-instances.....	95
euca-reboot-instances.....	96
euca-register.....	97
euca-release-address.....	99
euca-reset-image-attribute.....	100
euca-resume-import.....	101
euca-revoke.....	102
euca-run-instances.....	104
euca-start-instances.....	107
euca-stop-instances.....	108
euca-terminate-instances.....	109
euca-unbundle.....	110
euca-unbundle-stream.....	112
euca-unmonitor-instances.....	113
euca-upload-bundle.....	114
euca-version.....	115

IAM-Compatible Commands..... 117

euare-accountaliascreate.....	117
euare-accountaliasdelete.....	118
euare-accountaliaslist.....	119
euare-accountcreate.....	120
euare-accountdel.....	121
euare-accountdelpolicy.....	121
euare-accountgetpolicy.....	122
euare-accountgetsummary.....	123
euare-accountlist.....	124
euare-accountlistpolicies.....	125
euare-accountuploadpolicy.....	126
euare-assumerole.....	127
euare-getldapsyncstatus.....	128
euare-groupaddpolicy.....	129
euare-groupadduser.....	130
euare-groupcreate.....	131
euare-groupdel.....	132
euare-groupdelpolicy.....	133
euare-groupgetpolicy.....	134
euare-grouplistbypath.....	135
euare-grouplistpolicies.....	136

euare-grouplistusers.....	137
euare-groupmod.....	138
euare-instanceprofileaddrole.....	140
euare-instanceprofilecreate.....	140
euare-instanceprofiledel.....	141
euare-instanceprofilegetattributes.....	142
euare-instanceprofilelistbypath.....	143
euare-instanceprofilelistforrole.....	144
euare-instanceprofileremoverole.....	145
euare-getcallerid.....	146
euare-groupremoveuser.....	147
euare-groupuploadpolicy.....	148
euare-releaserole.....	149
euare-roleaddpolicy.....	149
euare-rolecreate.....	150
euare-roledel.....	152
euare-roledelpolicy.....	153
euare-rolegetattributes.....	154
euare-rolegetpolicy.....	155
euare-rolelistbypath.....	156
euare-rolelistpolicies.....	157
euare-roleupdateassumepolicy.....	158
euare-roleuploadpolicy.....	158
euare-useraddcert.....	160
euare-useraddkey.....	161
euare-useraddloginprofile.....	162
euare-useraddpolicy.....	163
euare-usercreate.....	164
euare-usercreatecert.....	166
euare-userdel.....	168
euare-userdelcert.....	169
euare-userdelkey.....	170
euare-userdelloginprofile.....	171
euare-userdelpolicy.....	172
euare-usergetattributes.....	172
euare-usergetinfo.....	174
euare-usergetloginprofile.....	175
euare-usergetpolicy.....	176
euare-userlistbypath.....	177
euare-userlistcerts.....	178
euare-userlistgroups.....	179
euare-userlistkeys.....	179
euare-userlistpolicies.....	180
euare-usermod.....	181
euare-usermodcert.....	183
euare-usermodkey.....	184
euare-usermodloginprofile.....	185
euare-userupdateinfo.....	186
euare-useruploadpolicy.....	187
Elastic Load Balancing Commands.....	189
eulb-configure-healthcheck.....	189
eulb-create-lb.....	190
eulb-create-lb-listeners.....	191
eulb-create-lb-policy.....	192

eulb-create-tags.....	193
eulb-delete-lb.....	193
eulb-delete-lb-listeners.....	194
eulb-delete-tags.....	195
eulb-deregister-instances-from-lb.....	195
eulb-describe-instance-health.....	196
eulb-describe-lb-attributes.....	197
eulb-describe-lbs.....	198
eulb-describe-lb-policies.....	199
eulb-describe-tags.....	200
eulb-disable-zones-for-lb.....	200
eulb-enable-zones-for-lb.....	201
eulb-modify-lb-attributes.....	202
eulb-register-instances-with-lb.....	203

Auto Scaling-Compatible Commands.....204

euscale-create-auto-scaling-group.....	204
euscale-create-launch-configuration.....	205
euscale-delete-auto-scaling-group.....	207
euscale-delete-launch-configuration.....	208
euscale-delete-policy.....	209
euscale-describe-adjustment-types.....	210
euscale-describe-auto-scaling-instances.....	211
euscale-describe-auto-scaling-groups.....	212
euscale-describe-launch-configs.....	213
euscale-describe-metric-collection-types.....	214
euscale-describe-policies.....	215
euscale-describe-scaling-activities.....	216
euscale-describe-termination-policy-types.....	217
euscale-disable-metrics-collection.....	218
euscale-enable-metrics-collection.....	219
euscale-execute-policy.....	220
euscale-put-scaling-policy.....	221
euscale-resume-processes.....	222
euscale-set-desired-capacity.....	223
euscale-set-instance-health.....	224
euscale-suspend-processes.....	225
euscale-terminate-instance-in-auto-scaling-group.....	226
euscale-update-auto-scaling-group.....	227

CloudWatch-Compatible Commands.....230

euwatch-delete-alarms.....	230
euwatch-describe-alarm-history.....	231
euwatch-describe-alarms.....	232
euwatch-describe-alarms-for-metric.....	234
euwatch-disable-alarm-actions.....	235
euwatch-enable-alarm-actions.....	236
euwatch-get-stats.....	237
euwatch-list-metrics.....	239
euwatch-put-data.....	241
euwatch-put-metric-alarm.....	243
euwatch-set-alarm-state.....	244

CloudFormation-Compatible Commands..... 246

euform-cancel-update-stack.....	246
euform-create-stack.....	246
euform-delete-stack.....	248
euform-describe-stack-events.....	248
euform-describe-stack-resource.....	249
euform-describe-stack-resources.....	250
euform-describe-stacks.....	251
euform-get-template.....	252
euform-list-stack-resources.....	253
euform-list-stacks.....	253
euform-update-stack.....	254
euform-validate-template.....	255

Virtual Private Cloud (VPC)-Compatible Commands..... 257

euca-accept-vpc-peering-connection.....	257
euca-assign-private-ip-addresses.....	257
euca-associate-dhcp-options.....	259
euca-attach-internet-gateway.....	259
euca-attach-network-interface.....	260
euca-attach-vpn-gateway.....	260
euca-create-customer-gateway.....	261
euca-create-dhcp-options.....	262
euca-create-internet-gateway.....	263
euca-create-nat-gateway.....	264
euca-create-network-interface.....	265
euca-create-route.....	266
euca-create-route-table.....	267
euca-create-subnet.....	268
euca-create-vpc.....	269
euca-create-vpc-peering-connection.....	269
euca-create-vpn-connection-route.....	270
euca-create-vpn-connection.....	271
euca-create-vpn-gateway.....	272
euca-delete-customer-gateway.....	273
euca-delete-dhcp-options.....	274
euca-delete-internet-gateway.....	274
euca-delete-network-interface.....	275
euca-delete-vpc.....	276
euca-delete-vpc-peering-connection.....	277
euca-delete-vpn-connection-route.....	277
euca-delete-vpn-connection.....	278
euca-delete-vpn-gateway.....	279
euca-describe-account-attributes.....	280
euca-describe-customer-gateways.....	280
euca-describe-dhcp-options.....	282
euca-describe-internet-gateways.....	284
euca-describe-network-interface-attribute.....	285
euca-describe-network-interfaces.....	286
euca-describe-vpc-attribute.....	289
euca-describe-vpcs.....	290
euca-describe-vpc-peering-connections.....	291
euca-describe-vpn-connections.....	293

euca-describe-vpn-gateways.....	295
euca-detach-internet-gateway.....	296
euca-detach-network-interface.....	297
euca-detach-vpn-gateway.....	297
euca-disable-vgw-route-propagation.....	298
euca-enable-vgw-route-propagation.....	299
euca-modify-network-interface-attribute.....	300
euca-modify-vpc-attribute.....	301
euca-reject-vpc-peering-connection.....	302
euca-reset-network-interface-attribute.....	302
euca-unassign-private-ip-addresses.....	303
 Euca2ools Guide History.....	 305

Euca2ools Overview

Welcome to the Euca2ools Reference Guide. This guide provides an overview of the Eucalyptus command line interface (Euca2ools), including installation and configuration instructions. It also describes the syntax and parameters for each command.

The following topics contain information on how to install and configure Euca2ools.

This is Euca2ools Guide version Build 30 (2020-12-03 17:50:50 UTC)

Overview of Euca2ools

Euca2ools is the Eucalyptus command line interface for interacting with web services.

Most Euca2ools commands are compatible with Amazon's EC2, S3, IAM, Auto Scaling, Elastic Load Balancing, CloudFormation, Virtual Private Cloud (VPC), and CloudWatch services and generally accept the same options and honor the same environment variables. This means that you can use Euca2ools with both the Eucalyptus cloud-computing platform and compatible Amazon services. A few commands are specific to Eucalyptus and are noted in the command description.

Note: Some operations in Euca2ools are not supported in certain Eucalyptus networking modes. For example, security groups and elastic IPs are not supported in both Static and System networking modes. See your cloud administrator for details. For more information about networking modes, see [Plan Networking Modes](#).

This set of tools was written in Python.

Installing Euca2ools

This section covers how to install Euca2ools.

Installing Euca2ools on RHEL / CentOS

Euca2ools is included with package installations of Eucalyptus. Please check with your administrator to confirm that Euca2ools is installed properly on your client machine.

To install Euca2ools on RHEL / CentOS using Eucalyptus-provided packages:

1. Install the EPEL package repository:

```
yum install http://dl.fedoraproject.org/pub/epel/epel-release-latest-7.noarch.rpm
```

2. Install the euca2ools package repository:

```
yum install http://downloads.eucalyptus.cloud/software/euca2ools/3.4/rhel/7/x86_64/euca2ools-release-3.4-2.2.as.el7.noarch.rpm
```

3. Install the euca2ools package:

```
yum install euca2ools
```

Installing Euca2ools on Mac OS X

This task shows you how to install Euca2ools on Mac OS X.

To install Euca2ools on Mac OS X:

1. Download and extract the Euca2ools tar file:

```
curl -O http://downloads.eucalyptus.com/software/euca2ools/3.4/source/
euca2ools-3.4.1.tar.xz
```

2. Extract the Euca2ools tar file and change to the euca2ools directory:

```
tar xf euca2ools-3.4.1.tar.xz
cd euca2ools-3.4.1
```

3. **Note:** If you have Xcode installed, be sure to install the Xcode command line tools by opening the Xcode **Preferences** menu, selecting **Downloads**, selecting **Components**, and then clicking the **Install** button next to **Command Line Tools** in the components list. If you are using Mavericks, go to [Install Command Line Tools In OSX 10.9 Mavericks \[How - To \]](#) for this information.

Switch to the directory where you extracted the Euca2ools tar file and install Euca2ools using the following command.

```
sudo python setup.py install
```

4. Type the following command to verify Euca2ools installed properly:

```
euca-version
```

This command should return output similar to the following:

```
euca2ools 3.4.1
```

You've now installed Euca2ools. If you haven't already done so, you will need to set up your service endpoints and credentials. For more information, see [Working with Euca2ools Configuration Files](#) and the [IAM-Compatible Commands](#).

Configuring Euca2ools

This section covers how to configure Euca2ools.

Setting Environment Variables

Euca2ools uses two kinds of credentials to authenticate user identity: X.509 PEM-encoded certificates and access keys. In addition, you must also specify service endpoints.

You must either define a set of environment variables in advance or use command-line options to allow Euca2ools to communicate with the cloud and verify user identity.

For more information, see [Working with Euca2ools Configuration Files](#) and the [IAM-Compatible Commands](#).

Variable	Option	Description
EC2_URL	-U, --url <url>	http://<host_ip>:8773/services/compute
S3_URL	-U, --url <url>	http://<host_ip>:8773/services/Walrus
AWS_IAM_URL	-U, --url <url>	http://<host_ip>:8773/services/Euare
AWS_AUTO_SCALING_URL	-U, --url <url>	http://<host_ip>:8773/services/ AutoScaling
AWS_ELB_URL	-U, --url <url>	http://<host_ip>:8773/services/ LoadBalancing
AWS_CLOUDWATCH_URL	-U, --url <url>	http://<host_ip>:8773/services/ CloudWatch
EUCALYPTUS_CERT	--ec2cert_path <file>	Path to cloud certificate
EC2_CERT	-c, --cert <file>	Path to your PEM-encoded certificate

Variable	Option	Description
EC2_PRIVATE_KEY	-k, --privatekey <file>	Path to your PEM-encoded private key
AWS_ACCESS_KEY	-a, --access-key <key>	Your access key ID
AWS_SECRET_KEY	-s, --secret-key <key>	Your secret access key

Order of Precedence for Common Parameters

The following lists show the order of precedence that Euca2ools commands use to retrieve the URL, region name, and access key values when running commands.

URL and Region Name Order of Precedence

1. The `--url` parameter specified with the command
2. Configuration file for region given with `--region`
3. The service URL environment variable (for example: `EC2_URL`)
4. Configuration file for region given with `AWS_DEFAULT_REGION` environment variable
5. Configuration file default region

Access Key Order of Precedence

1. Command line arguments (for example: `--secret-key`)
2. Environment variables (for example: `AWS_ACCESS_KEY`)
3. Configuration file settings for user/region given with `--region`
4. The `AWS_CREDENTIAL_FILE`
5. Configuration file for region given with `AWS_DEFAULT_REGION` environment variable
6. Configuration file settings for the default user and region

Working with Euca2ools Configuration Files

Euca2ools supports the use of configuration files to make it easy to switch between users and cloud configurations from the command line. The euca2ools configuration file allows you to store credentials and URLs for multiple users and regions, and then switch between cloud configurations by using the `--region` option with your euca2ools commands.

This section discusses how to work with Euca2ools configuration files.

- [Configuration File Locations](#)
- [Configuration File Contents](#)
- [Using Euca2ools Configuration Files](#)

Configuration File Locations

Euca2ools supports multiple configuration files. The configuration files are read in alphabetical order from the following locations:

1. `/etc/euca2ools/euca2ools.ini`
2. `/etc/euca2ools/conf.d/*.ini`
3. `~/.euca/*.ini`

Note that only the `euca2ools.ini` file is read in the `/etc/euca2ools` directory; in the other directories any file ending with `.ini` is read.

Euca2ools will combine all of the configuration files it finds in these directories. In cases where there the same setting is defined twice in the configuration files, the most recently read file will take precedence.

The Euca2ools package ships with an example `/etc/euca2ools/euca2ools.ini` file that is empty, and `.ini` files in `/etc/euca2ools/conf.d` that contain pre-defined configuration for AWS and the Eucalyptus Community Cloud.

Configuration File Contents

There are three section types in a euca2ools configuration file: global, region, and user.

The user and region sections are named sections - you must specify a name for each of these sections. For example:

```
[user myusername]
[region ecc]
```

Note: The user and region section names cannot contain @, : or white space.

You can have as many named region and user sections as you need.

The **region** sections contain service URLs for the named region, as well as a reference to a named user section that contains the user's account ID and credentials. Once you've defined regions and users in the configuration file, you can specify the named region using the `--region` command line option or the `EUCA_REGION` environment variable. When you supply a region name it will use the URLs defined in the configuration file for that named region, and (unless overridden) the credentials from the user that region refers to (as defined by the user named in that region's definition).

The `--region` parameter lets you choose specific combinations of the users and regions defined in the configuration file with the format "user@region". For example:

This example will use the ecc region:

```
euca-describe-instances --region ecc
```

The following example will use the user defined in the [user jdoe] section of the configuration file with the region defined in the [region us-west-2] section of the configuration file:

```
euca-describe-instances --region jdoe@us-west-2
```

In this example, the user defined in the [user jdoe] section of the configuration file will be used with the default region specified in the **global** section of the configuration file:

```
euca-describe-instances --region jdoe@
```

If you don't supply a region you get the global default region (as defined in the global section of the configuration file).

If you don't supply a user at the command line, your command will use the region's default user.

Region Naming Rules for AWS

When naming region sections for use with AWS, the region name has to agree with the name assigned to the region by AWS if the AWS service uses signature version 4. You can add a "name" option to a region definition in the configuration file to explicitly tell euca2ools what name to send the server.

Reusing Options

You can re-use an option from another region in your region definition by using the 'use' keyword.

In the following example, the `us-west-1` region is using the `iam-url` value defined in the `us-east-1` section:

```
[region us-east-1]
iam-url = https://iam.amazonaws.com/
[region us-west-1]
iam-url = use us-east-1
```

Wildcard and Grouped Names

You can use "[region *]" or "[user *]" to refer to all regions or users. This is not the same as putting something in the "[global]" section. The more specific the user or region section's name is, the higher precedence it has, so options under "[user jdoe]" take precedence over those under "[user *]".

You can organize regions and users in the config files into groups, separated by : characters. For example:

```
[region aws:us-east-1]
...
[region aws:us-west-1]
...
[region aws:*]
...
```

When section names contain wildcards, the most specific name takes precedence; for example, `aws:us-east-1` takes precedence over `aws:*`.

When you refer to a region or user by a name like "us-east-1" and there isn't any configuration that exactly matches that name, euca2ools will attempt to find the closest match. For example, with only the configuration above, if you supply "`--region us-east-1`" at the command line it will use the configuration under "aws:us-east-1", but if you were to add "foo:us-east-1" then this would become ambiguous and result in an error.

The global Section

The global section of the Euca2ools configuration file contains settings that affect all operations and the defaults to use when more explicit parameters are not supplied (for example, the default region).

The following table lists the possible parameters that you can specify in the global section of the Euca2ools configuration file:

Parameter	Description
<code>debug</code>	Indicates whether to enable debug message output. Set this to <code>false</code> to disable debug output, <code>true</code> to enable debug output, or <code>color</code> to enable debug output and additionally colorize it with ANSI color codes. The default is <code>false</code> .
<code>default-region</code>	The name of the region to use when no region is specified.
<code>max-retries</code>	The maximum number of times commands should retry their requests to the server when the server encounters an error. The default is 2.
<code>timeout</code>	The amount of time, in seconds, to wait for the server to respond to a request before the command gives up and returns an error. The default timeout is 30.

The user Section

The user section of the Euca2ools configuration file contains account credentials and keys for a specific user. A user section can be referenced in a region section definition so that user's credentials will be used when the region is specified on the command line using the `--region` option.

The following table lists the possible parameters that you can specify in the user section of the Euca2ools configuration file:

Parameter	Description
<code>account-id</code>	The user's numeric account number / ID.
<code>key-id</code>	The user's access key ID. Most commands require an access key ID, along with a secret key.
<code>secret-key</code>	The user's secret key. Most commands require a secret key, along with an access key ID.
<code>certificate</code>	The user's signing certificate, which euca-bundle-image uses when bundling images.

Parameter	Description
private-key	The user's private key, which euca-bundle-image and euca-unbundle use when bundling and unbundling images.

The region Section

The **region** section of the Euca2ools configuration file contains service URLs, user names, and other information for the named region. You can specify the named region on the command line using the `--region` option, or with the `EUCA_REGION` environment variable.

The following table lists the possible parameters that you can specify in the **region** section of the Euca2ools configuration file:

Parameter	Description
autoscaling-url	The URL for the region's auto scaling service.
cloudformation-url	The URL for the region's CloudFormation service.
ec2-url	The URL for the region's compute service.
elasticloadbalancing-url	The URL for the region's load balancing service.
iam-url	The URL for the region's identity and access management service.
monitoring-url	The URL for the region's metric/monitoring service.
s3-url	The URL for the region's object storage service.
s3-location-constraint	The location constraint needed to create buckets in the region's object storage service.
user	The default user for this region if no other user is specified. This name corresponds to a named user section in the configuration file that contains the user's credentials.
verify-ssl	Indicates whether to verify the server's SSL certificate. This can be <code>true</code> or <code>false</code> ; the default is <code>false</code> .
certificate	Location of the cloud's certificate, which <code>euca-bundle-image</code> uses when bundling images. Eucalyptus frequently uses a file named <code>cloud-cert.pem</code> .
s3-force-sigv4	Force commands that access the s3 service to use AWS signature version 4. The default is <code>false</code> .
vpn-stylesheet	The location of the XSLT stylesheet for the <code>euca-create-vpn-connection</code> or <code>euca-describe-vpn-connections</code> commands to use to reformat VPN connection information. If the location is an HTTP or HTTPS URL it will be downloaded as needed. If it contains "{format}" that will be replaced with the desired format.

Using Euca2ools Configuration Files

The following examples show how to set up a basic Euca2ools configuration file.

1. Open a text editor and add a `[user]` section. For example:

```
[user john]
key-id = AKIA93F29V0AEXAMPLE
secret-key = vcasd93cm1458un4vj84039vda78mDEXAMPLE
```

Once you've defined a user in a configuration file, you can specify this user from any subsequent [region] section in the configuration file.

2. Add a [region] section to a configuration file. Be sure to add a user entry that points to a user already defined in a config file; Euca2ools will use this user's credentials to access to the cloud specified in this region section. For example:

```
[region us-east-1]
ec2-url = https://ec2.amazonaws.com/
iam-url = https://iam.amazonaws.com/
s3-url = https://s3.amazonaws.com/
user = john
```

Once you've set up a user and a region in the configuration file, you can easily switch between regions using the --region option from any euca2ools command.

3. Add a [global] section to specify which region to use when you don't specify the --region option on the command line. For example:

Note: Any euca2ools commands entered without specifying the --region option will result in an error.

```
[global]
default-region = us-east-1
```

The following example shows an example of a complete euca2ools configuration file.

```
[user john]
key-id = AKIA93F29V0AEXAMPLE
secret-key = vcasd93cm1458un4vj84039vda78mDEXAMPLE
[user fry]
[region us-east-1]
autoscaling-url = https://autoscaling.us-east-1.amazonaws.com/
ec2-url = https://ec2.us-east-1.amazonaws.com/
elasticloadbalancing-url = https://elasticloadbalancing.us-east-1.amazonaws.com/
iam-url = https://iam.amazonaws.com/
monitoring-url = https://monitoring.us-east-1.amazonaws.com/
s3-url = https://s3.amazonaws.com/
user = john
[region ecc]
autoscaling-url =
https://communitycloud.eucalyptus.com:8773/services/AutoScaling/
ec2-url = https://communitycloud.eucalyptus.com:8773/services/
Eucalyptus/
elasticloadbalancing-url =
https://communitycloud.eucalyptus.com:8773/services/LoadBalancing/
iam-url = https://communitycloud.eucalyptus.com:8773/services/
Euare/
monitoring-url = https://communitycloud.eucalyptus.com:8773/
services/Monitoring/
s3-url = https://communitycloud.eucalyptus.com:8773/services/
Walrus/
user = john
[global]
default-region = us-east-1
```

To use the configuration file, simply specify one of the named regions by using the --region option with any euca2ools command. For example:

```
euca-describe-instances --region ecc
```

This command will use the use the service URLs and user credentials specified in the "ecc" region and "ecc-admin" user sections in the configuration file.

EC2-Compatible Commands

The basic set of Euca2ools begin with the `euca -` prefix. These commands are compatible with Amazon EC2.

euca-allocate-address

Allocates an elastic IP address. The output returns the IP address that was allocated.

Syntax

```
euca-allocate-address [-d vpc]
```

Options

Option	Description	Required
<code>-d, --vpc <i>vpc</i></code>	(VPC only) Specifies that this address is to be allocated for use in a VPC.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("ADDRESS")
- Elastic IP address for use with your account, followed by the domain for the IP address (either "vpc" or "standard")
- If the address is a VPC address, the allocation ID for the address

Example

```
euca-allocate-address
ADDRESS 10.103.4.105 standard
```

euca-associate-address

Associates an elastic IP address with an instance. This assumes that the address you supplied has already been allocated with the `euca-allocate-address` command.

Syntax

```
euca-associate-address -i instance_id [-n interface] [-a allocation] [-p address] [--allow-reallocation] ip
```

Options

Option	Description	Required
<code>-i, --instance</code>	Unique identifier for a running instance to associate the address with.	Yes
<code>-n, --network-interface <i>interface</i></code>	(VPC only) The network interface to associate with the address.	Yes, if VPC
<code>-a, --allocation-id <i>alloc</i></code>	(VPC only) The VPC allocation ID.	No
<code>-p, --private-ip-address <i>address</i></code>	(VPC only) The private address to associate with the address being associated in the VPC. This defaults to the primary private IP address.	No
<code>--allow-reassociation</code>	(VPC only) Allow the address to be associated even if it is already associated with another instance.	No
<code>ip</code>	Elastic IP address to associate	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.

Option	Description
- -debugger	Enable interactive debugger on error.
-h, - -help	Display the manual page for the command.
- -version	Display the version of this tool.

Output

- Output type identifier ("ADDRESS")
- IP address
- Instance ID

Example

```
euca-associate-address -i i-3C66428A 86.75.30.9
ADDRESS 86.75.30.9 i-3C66428A
```

euca-attach-volume

Attaches an EBS volume to an instance. Not all volumes can be attached using this command; /dev/sda and /dev/sdb are restricted.

Syntax

```
euca-attach-volume -i instance_id -d device volume_id
```

Options

Option	Description	Required
-i, - -instance	Unique ID of a running instance to attach the volume to.	Yes
-d, - -device	Local device name (inside the guest VM) to use. Depending on your hypervisor, this might be ignored.	Yes
volume_id	Unique id for the volume to be attached.	Yes

Common Options

Option	Description
- -show-empty-fields	Show empty fields as "(nil)".
- -region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, - -url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, - -access-key-id <i>key_id</i>	User's access key ID.
-S, - -secret-key <i>secret_key</i>	User's secret key.
- -security-token <i>token</i>	User's security token.

Option	Description
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("VOLUME")
- Volume ID

Example

```
euca-attach-volume -i i-3C66428A -d /dev/sdf vol-639C3E6C
VOLUME vol-639C3E6C
```

euca-authorize

Adds a rule to a security group that allows traffic to pass.

Syntax

```
euca-authorize group_name [-P {tcp,udp} -p port_range] [-s cidr_range]
```

```
euca-authorize group_name [-P icmp -t type:code] [-s cidr_range]
```

Options

Option	Description	Required
group_name	Name of the security group to add the rule to.	Yes
- -egress	(VPC only) Manage an egress rule, which controls traffic leaving the group. Default: If this option is not specified, the rule is an ingress rule (applies to traffic entering the group).	No
-P, --protocol <i>protocol</i> <i>protocol_number</i>	IP protocol name or number. Valid values: tcp udp icmp -1/all Note: You can specify arbitrary <u>IANA-assigned protocol numbers</u> as well as the special values "all" and "-1", which refer to all network traffic, in VPC security groups. As a convenience, if a protocol is specified by name euca-authorize and euca-revoke will consult /etc/protocols to discover its number.	No
-p <i>port_range</i>	Specifies the range of ports to allow for TCP and UDP. Not valid for ICMP. Valid values: Single integer or range (min-max). Use -1 to specify all ports.	Conditional

Option	Description	Required
<code>-t, --icmp-type-code</code>	ICMP type and code specified as "type:code". Only works if you specify ICMP as the protocol.	Conditional
<code>-o, --source-group <i>source_group</i></code>	(Non-VPC only) Group from which traffic is authorized by the rule. Every instance in the security group is allowed to pass traffic.	No
<code>-u, --source-group-user <i>source_group_user</i></code>	ID of the security group user you name in the -o parameter	No
<code>-s, --source-subnet <i>source_subnet</i></code>	Addresses to apply the rule to Default: 0.0.0.0/0	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("GROUP", "PERMISSION")
- Group name
- Rule type (EC2 only supports an ALLOW rule)
- Protocol
- Port range start
- Port range end

Example

```
euca-authorize default -P tcp -p 80 -s 0.0.0.0/0
GROUP    default
PERMISSION default  ALLOWS  tcp 80  80  FROM    CIDR    0.0.0.0/0
```

```
euca-authorize -P tcp -p 6697-7000 -s 1.2.3.0/24 mygroup
GROUP      mygroup
PERMISSION mygroup ALLOWS tcp 6697 7000 FROM CIDR 1.2.3.0/24
```

```
euca-authorize -P icmp -t 0:0 -o othergroup -u 1234567890 mygroup
GROUP      mygroup
PERMISSION mygroup ALLOWS icmp      USER      1234567890      GRPNAME othergroup
FROM      CIDR      0.0.0.0/0
```

euca-bundle-image

Bundles an image for use with Eucalyptus or Amazon EC2.

Syntax

```
euca-bundle-image -i image_path -r [i386,x86_64,armhf]
[-u, --user account-id]
[-p, --prefix prefix][--kernel kernel_id]
[--ramdisk ramdisk_id]
[--product-codes product_codes]
[-B, --block-device-mapping mapping]
[-d, --destination destination]
[--ec2cert ec2cert_path ][--batch]
```

Options

Option	Description	Required
-i, --image	Path to the image file to bundle. If a dash ("-") is provided, stdin will be used, and the --prefix and --image-size parameters are required.	Yes
-p prefix, --prefix prefix	The file name prefix to give the bundle image files. Required when bundling stdin; otherwise defaults to the image's file name.	Conditional
-d directory, --destination directory	Directory where the bundle image files go. Eucalyptus recommends that you include this option where allowed. This is the directory specified by TMPDIR, TEMP, or TMP environment variables. Default: /var/tmp	No
-r architecture, --arch architecture	Target architecture for the image. Default: x86_64 Valid values: i386 x86_64 armhf ppc ppc64	Yes
-u account, --user account	12-digit account ID of the person who is bundling the image.	No
-c file, --cert file	File containing your X.509 certificate.	No
--ec2cert file	File containing your cloud's X.509 certificate.	No
-k file, --privatekey file	File containing your private key to sign the bundle's manifest with. This private key will also be required to unbundle the image in the future.	No

Option	Description	Required
<code>--kernel</code>	ID of the kernel you want to associate with the image. You can override this ID in euca-register and euca-run-instances at runtime. If you are bundling a kernel image, set to <code>true</code> .	No
<code>--ramdisk</code>	ID of the ramdisk to be associated with the image. You can override this ID in euca-register and euca-run-instances at runtime. If you are bundling a ramdisk image, set to <code>true</code> .	No
<code>-B, --block-device-mapping</code>	Default block device mapping for the image. The format of the mapping is a comma-separated list of key=value pairs.	No
<code>--batch</code>	Run in batch mode. This is for compatibility only, and has no effect.	No
<code>- \-productcodes <i>code1</i> [<i>code2</i>, ...]</code>	Comma-delimited list of product codes.	No
<code>--image-size <i>size</i></code>	The size of the image. Required when reading from <code>stdin</code> .	Conditional
<code>--progress</code>	Show a progress bar during command execution. This is the default when this command is run interactively.	No
<code>--no-progress</code>	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Example

This command displays a progress bar while the image file is uploaded. For example:

```
[root@c-31 ~]# euca-bundle-image --arch i386 -i test.img
37% |=====| 3.75 GB 151.70 MB/s ETA:
0:00:44
```

This is followed by output that looks similar to the following example:

```
100% |=====| 10.00 GB 151.06 MB/s Time:
0:01:11
Wrote /var/tmp/bundle-cUuznJ/test.img.part.0
Wrote manifest /var/tmp/bundle-cUuznJ/test.img.manifest.xml
```

Once the initial upload is complete, you can use [euca-describe-bundle-tasks](#) to check on pending bundle tasks.

euca-bundle-instance

Bundles a running instance into a machine image and stores the image in object storage service. This command is typically used with Windows instances.

Syntax

```
euca-bundle-instance instance_id -b bucket -p prefix -o access_key_id -
c policy
-s signature -w secret_key -x expires
```

Options

Option	Description	Required
<i>instance_id</i>	ID of the instance you want to bundle	Yes
-b, --bucket <i>bucket_name</i>	Name of the bucket to upload.	Yes
-p, --prefix	The prefix for the bundle image files.	Yes
-o, --access-key-id <i>access_key_id</i>	Access key ID of the owner of the bucket	Yes
-c, --policy <i>policy</i>	Base64-encoded upload policy that allows the server to upload a bundle on your behalf. If unused, the -w parameter is required.	Conditional
-s, --policy-signature <i>signature</i>	The signature of the Base64-encoded upload policy. If unused, the -w parameter is required.	Conditional
-w, --secret-key <i>secret_key</i>	The bucket owner's secret access key, used to sign the upload policy. This parameter is required unless both the -c and the -s parameters are specified.	Conditional
-x, --expires	Expiration, in hours, for the generated upload policy. Default value is 24.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("BUNDLE")
- Bundle ID
- Instance ID
- Bucket name
- Bundle prefix
- State
- Bundle start time
- Bundle update time
- Bundle task state
- Bundle task progress

Example

```
euca-bundle-instance -b mah-bukkit -p windows -o
JCCBLEOQTLCFVNDPWUOG7 -w ZNpf50R3MmhA56YIMWd8ZmpucIW8NxYl84XT6l8N
i-E7AC420A
BUNDLE bun-CFF03DFA i-E7AC420A mah-bukkit winemi pending
2012-01-01T00:00:00.000Z 2012-01-01T00:00:00.000Z
```

euca-bundle-and-upload-image

Prepares and uploads an image for use in the Eucalyptus cloud.

Syntax

```
euca-bundle-and-upload-image -i filename [--preserve-bundle]
[--max-pending-parts max_pending_parts]
```

```

[-p prefix] [-d DIR] [-k filename]
-r {i386,x86_64,armhf,ppc,ppc64}
[-c filename] [--ec2cert filename] [-u account]
[--kernel image] [--ramdisk image]
[--block-device-mapping virtual1=device1,[virtual2=device2,...]]
[--productcodes code1,code2,...]
[--image-size image_size] -b bucketname[/PREFIX]
[--acl {public-read,aws-exec-read,ec2-bundle-read}]
[--upload-policy polycyname | --upload-policy-file filename]
[--upload-policy-signature signature]
[--location location] [--retry]
[--progress | --no-progress] [-U URL]
[--region user@region] [-I key_ID]
[-S key] [--security-token token]
[--debug] [--debugger] [--version] [-h]

```

Options

Option	Description	Required
-i, --image	Path to the image file to prepare.	Yes
-r, --arch	Architecture of the image to bundle. Valid values: i386, x86_64, armhf, ppc, ppc64	Yes
-b <i>bucket</i> [/ <i>prefix</i>]	Bucket to upload the bundle to.	Yes
-u, --user	12-digit account ID of the person who is bundling the image.	No
-c <i>file</i> , --cert <i>file</i>	File containing your X.509 certificate.	No
-k <i>file</i> , --privatekey <i>file</i>	File containing your private key to sign the bundle's manifest with. This private key will also be required to unbundle the image in the future.	No
-p <i>prefix</i> , --prefix <i>prefix</i>	The file name prefix to give the bundle image files. Required when bundling <code>stdin</code> ; otherwise defaults to the image's file name.	Conditional
--kernel	ID of the kernel you want to associate with the image. You can override this ID in euca-register and euca-run-instances at runtime. If you are bundling a kernel image, set to <code>true</code> .	No
--ramdisk	ID of the ramdisk to be associated with the image. You can override this ID in euca-register and euca-run-instances at runtime. If you are bundling a ramdisk image, set to <code>true</code> .	No
-B, --block-device-mapping	Default block device mapping for the image. The format of the mapping is a comma-separated list of key=value pairs.	No
-d, --destination	Directory to store bundle files. Defaults to the <code>TMPDIR</code> , <code>TEMP</code> , or <code>TMP</code> environment variables; if those are not present, defaults to <code>/var/tmp</code> .	No
--ec2cert <i>file</i>	File containing your cloud's X.509 certificate.	No
--batch	Run in batch mode. This is for compatibility only, and has no effect.	No
--productcodes <i>code1</i> [, <i>code2</i> , ...]	Comma-delimited list of product codes.	No

Option	Description	Required
<code>--progress</code>	Show a progress bar during command execution. This is the default when this command is run interactively.	No
<code>--no-progress</code>	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No
<code>--acl</code>	Pre-defined ACL policy to apply to the bundle. Valid values: <code>public-read</code> , <code>aws-exec-read</code> , <code>ec2-bundle-read</code> Default value: <code>aws-exec-read</code>	No
<code>--upload-policy</code>	S3 post policy to use for upload authorization, in JSON format.	No
<code>--upload-policy-file</code>	Filename of the file containing the S3 post policy file to use for upload authorization.	No
<code>--upload-policy-signature</code>	Signature for the S3 post policy. This parameter is required if <code>--upload-policy-file</code> or <code>--upload-policy</code> are specified.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

euca-bundle-vol

Bundles an image for use with Eucalyptus or Amazon EC2, compressing, encrypting and signing a snapshot of the local machine's root file system.

Syntax

```
euca-bundle-vol [-p PREFIX] [-d DIR] [-r {i386,x86_64,armhf,ppc,ppc64}]
                [-e PATH,...] [-i PATH,...] [-s MiB] [--no-filter]
                [--all] [--inherit | --no-inherit] [-v DIR]
                [-P {mbr,gpt,none}] [-S FILE]
                [--fstab FILE | --generate-fstab] [--grub-config FILE]
                [-k FILE] [-c FILE] [--ec2cert FILE] [-u ACCOUNT]
                [--kernel IMAGE] [--ramdisk IMAGE]
                [-B VIRTUAL1=DEVICE1,VIRTUAL2=DEVICE2,...]
                [--productcodes CODE1,CODE2,...]
                [--progress | --no-progress] [--debug] [--debugger]
                [--version] [-h]
```

Options

Option	Description	Required
<code>-p, --prefix <i>prefix</i></code>	File name prefix for the bundle files. Default is "image".	No
<code>-k, --privatekey <i>private_key</i></code>	Path to user's PEM-encoded private key.	Yes
<code>-u, --user <i>user_id</i></code>	12-digit account ID of the person who is bundling the image.	Yes
<code>-c, --cert</code>	Path the user's PEM-encoded certificate.	Yes
<code>-r <i>architecture</i>, --arch <i>architecture</i></code>	Target architecture for the image. Default: <code>x86_64</code> Valid values: <code>i386</code> <code>x86_64</code> <code>armhf</code> <code>ppc</code> <code>ppc64</code>	Yes
<code>-s, --size <i>size_in_mib</i></code>	Size of the image in MiB. Default: 10240 MiB	No
<code>-B, --block-device-mapping</code>	Default block device mapping for the image. The format of the mapping is a comma-separated list of key=value pairs.	No
<code>-d <i>directory</i>, --destination <i>directory</i></code>	Directory where the bundle image files go. Eucalyptus recommends that you include this option where allowed. This is the directory specified by <code>TMPDIR</code> , <code>TEMP</code> , or <code>TMP</code> environment variables. Default: <code>/var/tmp</code>	No
<code>-e, --exclude <i>directory_1</i>, <i>directory_2</i>,...</code>	Comma-separated list of directories to exclude. Default exclusions are stored in <code>/etc/euca2ools/bundle-vol/excludes</code> .	No
<code>-i, --include <i>directory_1</i>, <i>directory_2</i>,...</code>	Comma-separated list of directories to include.	No
<code>-a, --all</code>	Bundle all directories (including mounted filesystems).	No
<code>--inherit</code>	Explicitly inherit instance metadata and add it to the bundled image (this is the default behavior).	No
<code>--no-inherit</code>	Do not inherit instance metadata and add it to the bundled image.	No
<code>-P, --partition</code>	Which partition standard you want to use: Master Boot Record, GUID Partition Table, or no partition Valid values: <code>mbr</code> <code>gpt</code> <code>none</code>	

Option	Description	Required
<code>--no-filter</code>	Do not use the default filtered files list.	No
<code>--fstabpath</code>	Path to the fstab to bundle in the image.	No
<code>--generate-fstab</code>	Generate fstab to bundle in the image.	No
<code>--ec2certfile</code>	File containing the cloud's X.509 certificate.	No
<code>--kernelimage</code>	ID of the kernel image to associate with the machine bundle.	No
<code>--ramdiskimage</code>	ID of the ramdisk image to associate with the machine bundle.	No
<code>- \- productcodescode1 [, code2, ...]</code>	Comma-delimited list of product codes.	No
<code>--progress</code>	Show a progress bar during command execution. This is the default when this command is run interactively.	No
<code>--no-progress</code>	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No

Common Options

Option	Description
<code>--region region</code>	Region to direct requests to. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud to connect to. Expects an EC2 endpoint /services/Eucalyptus.
<code>-a, --access-key access_key_id</code>	User's access key ID
<code>-S, --secret-key secret_key</code>	User's secret key
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool

Output

Eucalyptus returns status messages describing the stages and status of the bundling.

Example

```
euca-bundle-vol -d /mnt/ebsvol -p myimage -s 2048 --arch x86_64
1+0 records in
1+0 records out
1048576 bytes (1.0 MB) copied, 0.00358811 s, 292 MB/s
mke2fs 1.41.9 (22-Aug-2009)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
131072 inodes, 524288 blocks
26214 blocks (5.00%) reserved for the super user
```

```

First data block=0
Maximum filesystem blocks=536870912
16 block groups
32768 blocks per group, 32768 fragments per group
8192 inodes per group
Superblock backups stored on blocks:
    32768, 98304, 163840, 229376, 294912

Writing inode tables: done
Creating journal (16384 blocks): done
Writing superblocks and filesystem accounting information: done

This filesystem will be automatically checked every 39 mounts or
180 days, whichever comes first.  Use tune2fs -c or -i to override.
Checking image
Tarring image
Encrypting image
Splitting image...
Part: myimage.part.0
Part: myimage.part.1
Part: myimage.part.2
Part: myimage.part.3
Part: myimage.part.4
Part: myimage.part.5
Part: myimage.part.6
Part: myimage.part.7
Part: myimage.part.8
Part: myimage.part.9
Part: myimage.part.10
Part: myimage.part.11
Part: myimage.part.12
Part: myimage.part.13
Part: myimage.part.14
Part: myimage.part.15
Part: myimage.part.16
Part: myimage.part.17
Part: myimage.part.18
Part: myimage.part.19
Part: myimage.part.20
Part: myimage.part.21
Part: myimage.part.22
Generating manifest /mnt/ebsvol/myimage.manifest.xml

```

euca-cancel-bundle-task

Cancels a previously submitted bundle task.

Syntax

```
euca-cancel-bundle-task bundle_id
```

Options

Option	Description	Required
<i>bundle_id</i>	ID of the bundle task to cancel	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("BUNDLE")
- Bundle ID
- Instance ID
- Bucket name
- Bundle prefix
- State
- Bundle start time
- Bundle update time
- Bundle task state
- Bundle task progress

Example

```
euca-cancel-bundle-task bun-CFF03DFA
BUNDLE bun-CFF03DFA i-E7AC420A mah-bukkit winemi cancelling
2012-01-01T00:00:00Z 2012-01-01T00:00:00Z
```

euca-cancel-conversion-task

Cancels a previously submitted bundle task.

Syntax

```
euca-cancel-conversion-task task_id
```

Options

Option	Description	Required
<i>bundle_id</i>	ID of the conversion task to cancel	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Example

```
euca-cancel-conversion-task bun-CFF03DFA
```

euca-create-group

Creates a new security group.

Syntax

```
euca-create-group group_name -d group_description [-c, --vpc VPC]
```

Options

Option	Description	Required
-d, --description	Description for the group to be created	Yes
<i>group_name</i>	Unique name for the group to be created	Yes
-v, --vpc <i>VPC</i>	(VPC only) The ID of the VPC in which to create the group.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("GROUP")
- Group name
- Group description

Example

```
euca-create-group mytestgroup -d "This is a test"
GROUP sg-EE57402E mytestgroup This is a test
```

euca-create-image

Creates a Eucalyptus Machine Image (EMI) from an EBS-based instance.

Syntax

```
euca-create-image instance_id -n, --name <name> [-b DEVICE=MAPPED] [--no-reboot] [-d, --description <description> ][-S, --secret-key <secret_key> ][-I <key_id>]
```

Options

Option	Description	Required
instance_id	The instance ID to use to create the EMI.	Yes
<code>-n, --name <i>name</i></code>	The name of the new image.	Yes

Option	Description	Required
<code>-d, --description description</code>	The description of the new image.	No
<code>--no-reboot</code>	Indicates that the instance should not be shut down before creating the image. Note: This may affect image integrity.	No
<code>-b, --block-device-mapping</code>	Block device mapping for the instance. This is passed in the form of <code><devicename>=<blockdevice></code> , where: <code>devicename</code> is the device name of the physical device on the instance to map and <code>blockdevice</code> is one of the following values: <code>none</code>: Use this value to suppress existing mapping on the specified image for this device. For example: <code>/dev/sdc=none</code> <code>ephemeral[0..3]</code>: Use this value to indicate that an instance local storage device should be mapped to this device. For example: <code>/dev/sdc=ephemeral0</code> <code>[snapshot-id]:[size]:[delete-on-termination (true false)]</code>: Use this value to map a device to an existing EBS-backed volume, and to specify whether the EBS volume should be deleted on termination. This value defaults to <code>true</code>. To specify a new EBS-backed volume, skip the snapshot ID and pass in a volume size instead. For example: <code>/dev/sdb=:20</code>.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.

Option	Description
<code>--version</code>	Display the version of this tool.

euca-create-keypair

Creates a new keypair and then prints the private half of the keypair. Eucalyptus does not store this information. We recommend that you create a keypair file with read permissions restricted to the appropriate user, and write the output to this file.

Syntax

```
euca-create-keypair keypair_name [-f, --filename file]
```

Options

Options	Description	Required
<code>keypair_name</code>	Unique name for a keypair to be created.	Yes
<code>-f, --filename file</code>	Save the keypair to the named file.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("KEYPAIR")
- Key pair name
- Private key fingerprint
- Private key

Example

```
euca-create-keypair mykey
KEYPAIR mykey 52:5f:e7:03:67:ad:b5:f3:65:4b:94:77:90:61:5f:1e:44:96:74:62
-----BEGIN RSA PRIVATE KEY-----
MIIIEowIBAAKCAQEAt5bLg1PhtF+kM5toDDL/MrxV5Ukm3ELWbI794MaCrFTiNTDf
URvZrWaKG2u1ldiHzJRhLusaUSopqdnCIW4hM5GJL1HRUZKy5cv3cNr1cf+NAuDEY
5iPzXwVW2I1masldmSwL5XWnehiigFveLkUqzsNEyKBVoi1DU0TNm1FZ0ee2w01A
wJOeAViz6itnCGbF0W9UhtCQ7Y1qP/ENcm96pqugsj11L04JMb+vX9Kc8VgHMBcb
1tg2kQShey28aJLXy9mu3RKL1lmd20yvxxY1PNVLjTpA0rzm0MKEG2S7H6im9v7Y
za6Tqik9WPi0jDcT/obwXLS+UgBpScai5179KwIDAQABAoIBAG1qhwJPNN5+fetv
/JQELIWVb5AGiA2QHCF5G2Aij3DL6kGPTkhWAwYbwTPFIt8Vv0G1sTH4Vqf2+/vJ1
4R7EXidjWhRV/JI/ywr4t4057iIe081LHa7T0FFaakcIBvkv6APJF5H7DASduAP0
PN3QxVGTWwRFAqR0W4K+J9eIEoMh1Tao6SKhpg8o8on2Iua+2PpYvK70ba8JBo/j
556o3sa0XIIlkpuzSKzRyABEi08hqUjkzhz16ep31F55neiW/y/kc3S0PjYrUg3f
mv/em3K12x1lRpkeo2lHiC27QblsDejrbIxr1yN7TRq9uWo6WxbBPR+6y0MNwgtz
Erflb7kCgYEA8/zH4l/18qheqowsfibeVcdxLTE/3i649ahdFGgWenr70P/xoBP5
GQ8wpzNXvDOLzmQPw4I4JrOid+qHg9y2gJi5KGBuUxrVAhH4uAleqXh1DbCIKfPg
GUN/n1ZkLm7N46NGf0zC0encEj1IvDFMGEQMRFBnXt1BA3eiWojBbL0CgYEAwKDA
ptz4SsDRlGt0+SfjIuUdPrP5DQAGvDkueLZ1TisTidavPcrTNS0Wm0GFnCCzW+4r
OqstJe4jpkwjcwB0KcyxrAex0twiYftFUAXbi8m5x1TsVzaN3C8RWPeNPs2QNqeZ
NC1UWIB+WOAyNs0x1CdNggkyMwdagH67fJfzVAcCgYAmTRhTwRyq6yNxQm/5ncBp
Vtw9cm3EQzF13vg9q91bgNLnDEayCnCGLnJEzRqIwM7Bp50R7W9DJA/tIzQCzzMX
H0J0JTRkd2HY4V1aCp6BnBTBAwVesJoNXts7mCRB5cMMaSU31zM+IKgbdONmJ5b6
eDQ0xSp1CUXbdXxXGgDDQKQBqQC9+gzmxMnQF+h15WInUtJtqN815x06YYtc+XZA
S6K3rD5B1EzSuYWiTuydZHqcZ5fdE8DoxK5G212ndjIECq+GRg34p0GA1njGf6V1
bcGAVTx2Qw0x+mjgjfj8yqjtQdDZF4Pd0/UnlwxzBFKQRZ0GuZfDITb+HmjoEvnio
QbxG4wKBgG0mAfkcFDyXBAx2J+oGoCe5EYT5KhceJK4U+RD+4nA9UeZAm29He9cC
G9xp8vetS78kFGMgbltbnMH7onznMM7/76x0a1Y04YQgCBGV9QsP1ViB0hCClPjHu
rt0p+0LncFC1gUInZvc3yEE10yYd9qDnaFCExxy5Bntc9Km+whQZ
-----END RSA PRIVATE KEY-----
```

euca-create-snapshot

Creates a snapshot from an existing volume.

Syntax

```
euca-create-snapshot volume_id [-d description ]
```

Options

Option	Description	Required
volume_id	Unique name for a volume to snapshot	Yes
-d, --description description	Description of the snapshot Constraints: up to 255 characters	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region user@region	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.

Option	Description
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("SNAPSHOT")
- Snapshot ID
- Source volume ID
- Snapshot status
- Snapshot process start time
- Snapshot process progress
- Snapshot owner's account ID
- Snapshot volume size
- Snapshot description

Example

```
euca-create-snapshot vol-84B54112
SNAPSHOT    snap-5E313F37    vol-84B54112    pending
2012-01-01T00:00:00.000Z    0%    None
```

euca-create-tags

Adds or overwrites one or more tags for the specified resource or resources

Syntax

```
euca-create-tags resource_id [resource_id ...] --tag key[=value] [--tag
key[=value] ...]
```

Options

Option	Description	Required
<code>resource_id</code>	ID of the resource you want to tag.	Yes

Option	Description	Required
<code>--tag key</code> or <code>key=value</code>	Key and optional value of the tag, separated by an equals sign (=). If you don't include a value, Eucalyptus sets the value to an empty string. If you're using Euca2ools on Windows, you might need to use quotation marks (for example, "key=value").	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("TAG")
- Resource type
- Resource ID
- Tag key
- Tag value

Example

```
euca-create-tags emi-1e2b3c4d i-7d3e5a2f --tag appserver --tag "stack=dev"
TAG image emi-1e2b3c4d appserver
TAG image emi-1e2b3c4d stack dev
TAG instance i-7d3e5a2f appserver
TAG instance i-7d3e5a2f stack dev
```

euca-create-volume

Creates a volume in a specified availability zone.

Syntax

```
euca-create-volume -z, --availability-zone zone [-s size ][--  
snapshot snapshot][-t, --type volume-type][-i, --iops IOPS]
```

Options

Option	Description	Required
-z, --availability-zone	Availability zone to create the volume in	Yes
-s, --size <i>size</i>	Size of the volume, in GiBs. You must specify either -s or --snapshot.	Conditional
--snapshot <i>snapshot</i>	Snapshot from which to create the new volume. You must specify either -s or --snapshot.	Conditional
-t, --type <i>volume-type</i>	The type of the volume. Valid values: standard io1. Default is standard.	No
-i, --iops <i>IOPS</i>	The number of I/O operations per second.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("VOLUME")
- Volume ID
- Volume size, in GiBs
- Source snapshot ID, if applicable
- Availability Zone
- Volume state

- Timestamp

Examples

```
euca-create-volume -z zone00 -s 5
VOLUME vol-84B54112 5 zone00 creating 2012-01-01T00:00:00.000Z
```

The following example shows a volume created from a snapshot.

```
euca-create-volume -z zone00 --snapshot snap-5E313F37
VOLUME vol-45C63B9B snap-5E313F37 zone00 creating
2012-01-01T00:00:00.000Z
```

euca-delete-bundle

Delete a previously uploaded bundle.

Syntax

```
euca-delete-bundle -b, --bucket bucket [-m, --manifest
manifest_path ][-p, --prefix prefix ][--clear]
```

Options

Option	Description	Required
-b, --bucket <i>bucket</i>	Name of the bucket the bundle is stored in	Yes
-m, --manifest <i>manifest_path</i>	Path to the manifest file. This is required if -p is not specified.	Conditional
-p, --prefix	The prefix for the bundle image files. This is required if -m is not specified.	Conditional

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.

Option	Description
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus displays status messages that indicate the status of the delete process.

Example

```
euca-delete-bundle -b mah-bukkit -m myimage.img.manifest.xml
```

euca-delete-disk-image

Deletes a disk image used for an import task.

Syntax

```
euca-delete-disk-image (-t task_id | -u manifest_URL)
[--ignore-active-task] [--s3-url URL]
[-o key_id] [-w key]
[-U URL] [--security-token token]
```

Options

Option	Description	Required
-t <i>task_id</i> , --task <i>task_id</i>	Identifier of the task to delete the image from.	Yes
-u <i>manifest_URL</i> , --manifest-url <i>manifest_url</i>	Location of the import manifest.	Yes
--ignore-active-task	Delete the image even if the import task is active. This only works when the --task parameter is specified.)	No
-U <i>url</i> , --url <i>url</i>	URL of the compute service endpoint.	No
--s3-url <i>url</i>	URL of the object storage service endpoint.	No
-o <i>key_id</i> , --owner-akid <i>key_id</i>	Access key to use for the object storage service.	No
-w <i>key</i> , --owner-sak <i>key</i>	Secret key to use for the object storage service.	No
--security-token <i>token</i>	The AWS delegation token.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.

Option	Description
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

euca-delete-group

Deletes a security group.

Syntax

```
euca-delete-group group_name | group_ID
```

Options

Option	Description	Required
<code>group_name</code> or <code>group_id</code>	Name or ID of the security group to be deleted	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.

Option	Description
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
-h, - -help	Display the manual page for the command.
- -version	Display the version of this tool.

Output

- Output type identifier ("GROUP")
- Group name

Example

euca-delete-group mytestgroup RETURN true

euca-delete-keypair

Delete an existing keypair

Syntax

```
euca-delete-keypair keypair_name
```

Options

Option	Description	Required
<i>keypair_name</i>	Unique name of the keypair to delete	

Common Options

Option	Description
- -show-empty-fields	Show empty fields as "(nil)".
- -region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, - -url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, - -access-key-id <i>key_id</i>	User's access key ID.
-S, - -secret-key <i>secret_key</i>	User's secret key.
- -security-token <i>token</i>	User's security token.
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.

Option	Description
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("KEYPAIR")
- Keypair name

Example

```
euca-delete-keypair mykey
KEYPAIR mykey
```

euca-delete-snapshot

Deletes a snapshot.

Syntax

```
euca-delete-snapshot snapshot_id
```

Options

Option	Description	Required
<i>snapshot_id</i>	Unique identifier for the snapshot to be deleted.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("SNAPSHOT")
- Snapshot ID

Example

```
euca-delete-snapshot snap-5E313F37
SNAPSHOT    snap-5E313F37
```

euca-delete-tags

Deletes the specified tags from the specified resource or resources. If you specify a value for the key, the tag is deleted only if the tag's value matches the one you specified. If you specify the empty string as the value, the tag is deleted only if the tag's value is the empty string.

Syntax

```
euca-delete-tags resource_id [resource_id ...] --tag key[=value] [--tag
key[=value] ...]
```

Options

Option	Description	Required
<code>resource_id</code>	ID of the resource you want to tag.	Yes
<code>--tag key</code> or <code>key=value</code>	Key and optional value of the tag, separated by an equals sign (=). You can enter more than one tag to remove.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

This command produces no output.

Examples

The following example specifies the empty string as the value for the tag to delete (notice the equals sign after Owner).

```
euca-delete-tags snap-4dfg39a --tag "Owner="
```

The following example deletes the `stack` tag from two instances, regardless of the values.

```
euca-delete-tags i-5f4e3d2a i-12345678 --tag stack
```

euca-delete-volume

Deletes a volume in a specified availability zone.

Syntax

```
euca-delete-volume volume_id
```

Options

Option	Description	Required
<i>volume_id</i>	Unique identifier for volume to be deleted	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("VOLUME")
- Volume ID

Example

```
euca-delete-volume vol-84B54112
VOLUME vol-84B54112
```

euca-deregister

Deregisters an image in the cloud.

Syntax

```
euca-deregister image_id
```

Options

Option	Description	Required
<i>image_id</i>	Unique identifier for image to be deregistered	

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("IMAGE")
- Image ID

Example

```
euca-deregister emi-15A1386E
IMAGE emi-15A1386E
```

euca-describe-addresses

Shows a list of public IP address that you have allocated. If you have assigned these to an instance, this list also includes the associated instance for each IP.

Syntax

```
euca-describe-addresses [ ip ] [[--filter "name=value"] ...]
```

Options

Option	Description	Required
<i>ip</i>	One or more elastic IP addresses or (VPC only) VPC allocation IDs.	No
-F, --filter name=value	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain elastic IP addresses. For example, you can use a filter to return only the addresses that have a specific tag. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for an address only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify addresses that have a specific tag. Eucalyptus responds with the information for an address only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-addresses`:

Filter	Description
<code>allocation-id</code>	(VPC only) A VPC allocation ID.
<code>association-id</code>	(VPC only) A VPC association ID.
<code>domain</code>	This filter is hardcoded to <code>standard</code> . There are no other valid values.
<code>instance-id</code>	ID of the instance associated with the IP address
<code>network-interface-id</code>	(VPC only) ID of the network interface associated with the IP address
<code>network-interface-owner-id</code>	(VPC only) ID of the network interface's owner
<code>private-ip-address</code>	(VPC only) The private IP address associated with the public IP address
<code>public-ip</code>	Elastic IP address

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("ADDRESS")
- Elastic IP address
- Instance ID that the IP address is assigned to
- IP address domain

Examples

As a user:

```
euca-describe-addresses
ADDRESS 86.75.30.9  None      standard
ADDRESS 86.75.30.10 i-E7AC420A      standard
```

As a cloud administrator:

```
euca-describe-addresses
ADDRESS 86.75.30.9  available
(arn:aws:euare::790547641019:user/admin)  standard
ADDRESS 86.75.30.10 i-E7AC420A
(arn:aws:euare::790547641019:user/admin)  standard
ADDRESS 86.75.30.11 nobody  standard
```

euca-describe-availability-zones

Shows information about availability zones.

Syntax

```
euca-describe-availability-zones [ zone ] [--filter "name=value" ...]
```

Options

Option	Description	Required
<i>zone</i>	One or more availability zone names. Leave blank to return all availability zones.	No
<i>-F, --filter name=value</i>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain availability zones. For example, you can use a filter to return only the availability zones that have a specific name. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for an availability zones only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify availability zones that have a specific tag. Eucalyptus responds with the information for an availability zone only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus\?\` searches for the literal string `*eucalyptus?\`.

The following are the available filters for `euca-describe-availability-zones`:

Filter	Description
<code>zone-name</code>	Name of the zone

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.

Option	Description
<code>- -version</code>	Display the version of this tool.

Output

- Output type identifier ("AVAILABILITYZONE")
- Availability zone name
- State of the availability zone

Example

As a user:

```
euca-describe-availability-zones
AVAILABILITYZONE    zone00    192.168.37.5
arn:euca:eucalyptus:zone00:cluster:zone00-cc00/
```

euca-describe-bundle-tasks

Describes currently submitted bundle tasks and their states.

Syntax

```
euca-describe-bundle-tasks [bundle ...] [--filter "name=value"] ...]
```

Options

Option	Description	Required
<i>bundle</i>	Identifier of the bundle task to describe. If you do not specify a bundle task ID, all bundle tasks are returned.	No
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain bundle tasks. For example, you can use a filter to return only the bundle tasks in the complete state. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a bundle task only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify bundles that are stored in a specific bucket and are in the complete state. Eucalyptus responds with the information for a bundle task only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-bundle-tasks`:

Filter	Description
<code>bundle-id</code>	ID of the bundle task

Filter	Description
error-code	If the task failed, returns the error code
error-message	If the task failed, returns the error message
instance-id	Instance ID that was bundled
progress	Level of task completion, in percent (for example, 20%)
s3-bucket	Bucket where the EMI will be stored
s3-prefix	Beginning of the AMI name
start-time	Time the task started
state	State of the task
update-time	Time of the most recent update for the task

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("BUNDLE")
- Bundle ID
- Instance ID
- Bucket name
- Image prefix
- Start time
- Update time
- Bundle state (pending, waiting-for-shutdown, bundling, storing, cancelling, complete, failed)
- Percentage progress, if state is "bundling"

Example

```
euca-describe-bundle-tasks
BUNDLE bun-CFF03DFA i-E7AC420A mah-bukkit winemi pending
2012-01-01T00:00:00.000Z 2012-01-01T00:00:00.000Z
```

euca-describe-conversion-tasks

Shows information about import operations.

Syntax

```
euca-describe-conversion-tasks task_id
```

Options

Option	Description	Required
<i>task_id</i>	Show information about the specified task.	No
-F, --filter <i>name=value</i>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Example

```
euca-describe-bundle-tasks
```

euca-describe-group

Shows information about one or more security groups.

Syntax

```
euca-describe-group [ group_name | group_ID ] [--filter "name=value"] ...]
```

Options

Option	Description	Required
group_name	Name or ID of a security group, if you want information about one particular group	No
-F, --filter name=value	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain groups. For example, you can use a filter to return only a group whose name contains a specific string. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a group only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify a group whose name matches a specific string, and also then give permission to another security group with a different string in its name that are stored in a specific bucket and are in the complete state. Eucalyptus responds with the information for a group only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `*eucalyptus?\` searches for the literal string `*eucalyptus?\`.

The following are the available filters for `euca-describe-group`:

Filter	Description
description	Description of the group
group-name	Name of the security group
ip-permission.cidr	CIDR range that has been granted the permission
ip-permission.from-port	Start of port range for the TCP and UDP protocols, or an ICMP type number. An ICMP type number of -1 indicates a wildcard (that is, any ICMP type number).
ip-permission.group-name	Name of security group that has been granted the permission
ip-permission.protocol	IP protocol for the permission Valid Values: tcp udp icmp
ip-permission.to-port	End of port range for the TCP and UDP protocols, or an ICMP code. An ICMP type number of -1 indicates a wildcard (that is, any ICMP type number).

Filter	Description
<code>ip-permission.user-id</code>	ID of Eucalyptus account that has been granted the permission
<code>owner-id</code>	Eucalyptus account ID of the owner of the security group
<code>tag-key</code>	Key of a tag assigned to the resource you want to filter. This filter is independent of the <code>tag-value</code> filter and returns all resources assigned the tag key you use, regardless of the value. To filter on a specific key and value set, use the <code>tag:key</code> filter.
<code>tag-value</code>	Value of a tag assigned to the resource. This filter is independent of the <code>tag-key</code> filter and returns all resources assigned the tag value you use, regardless of the key. To filter on a specific key and value set, use the <code>tag:key</code> filter.
<code>tag:key</code>	Filters the results based on a specific tag/value combination

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("GROUP")
- Account ID of the security group owner
- Security group name
- Security group description
- Output type identifier ("PERMISSION")
- Account ID of the security group owner
- Group name that is granting permission
- Rule type (only `ALLAWS` is supported)
- Protocol
- Port range start

- Port range end
- Source

Example

```
euca-describe-group scottb-test
GROUP      scottb-test ScottB Test
PERMISSION scottb-test ALLOWs tcp 22 22 FROM CIDR ingress
PERMISSION scottb-test ALLOWs tcp 3389 3389 FROM CIDR ingress
PERMISSION scottb-test ALLOWs tcp      FROM CIDR ingress
```

euca-describe-image-attribute

Show an image attribute. You can get information about only one attribute per request.

Syntax

```
euca-describe-image-attribute [-B, --block-device-mapping][-l,
--launch-permission][-p, --product-code][--kernel][--ramdisk] image_id
```

Options

Option	Description	Required
image_id	Unique identifier for the image that you want to retrieve the attributes for	Yes
-l, --launch-permission	Describes the launch permissions of the image	No
-p, --product-code	Describes the product code associated with the image	No
-B, --block-device-mapping	Describes mapping that defines device names to use when exposing virtual devices.	No
--kernel	Describe the kernel ID the image will be launched with	No
--ramdisk	Describe the RAM disk ID the image will be launched No with.	No
-F, --filter name=value	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region user@region	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url url	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id key_id	User's access key ID.

Option	Description
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Attribute type identifier
- Image ID
- Information about the attribute

Examples

Example using block device mapping:

```
euca-describe-image-attribute -B emi-815A395B
blockDeviceMapping emi-815A395B blockDeviceMap /dev/sda1: root
blockDeviceMapping emi-815A395B blockDeviceMap sda2: ephemeral0
blockDeviceMapping emi-815A395B blockDeviceMap sda3: swap
blockDeviceMapping emi-815A395B blockDeviceMap sda1: emi
```

Example using launch permission:

```
euca-describe-image-attribute -l emi-815A395B
launchPermission emi-815A395B group all
launchPermission emi-815A395B userId 790547641019
```

euca-describe-images

Shows information about an image you own, or an image you have been given permission to execute, or a public image owned by someone else.

Syntax

```
euca-describe-images [-a][--owner owner][--executable_by executable_by]
[ image ] [--filter "name=value" ...]
```

Options

Option	Description	Required
<code>image</code>	Image ID to describe	No
<code>-a, --all</code>	Describe all Eucalyptus machine images (EMIs)	No
<code>-o, --owner <i>owner</i></code>	Returns EMIs owned by the specified owner. Valid values: <code>self</code> <i>Account ID</i>	No

Option	Description	Required
<code>-x, --executable-by user_id</code>	Returns EMIs the specified user ID has launch permissions for	No
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain images. For example, you can use a filter to specify that you want to find images that use a specific kernel. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for an image only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify images that use a specific kernel and use an EBS volume as the root device. Eucalyptus responds with the information for an image only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?\`.

The following are the available filters for `euca-describe-images`:

Filter	Description
<code>architecture</code>	Image architecture. Valid values: <code>i386</code> <code>x86_64</code>
<code>block-device-mapping.delete-on-termination</code>	Whether the EBS volume is deleted on instance termination.
<code>block-device-mapping.device-name</code>	Device name (for example, <code>/dev/sdh</code>) for an EBS volume mapped to the image.
<code>block-device-mapping.snapshot-id</code>	Snapshot ID for an EBS volume mapped to the image.
<code>block-device-mapping.volume-size</code>	Volume size for an EBS volume mapped to the image.
<code>block-device-mapping.volume-type</code>	Volume type for an EBS volume mapped to the image. Valid values: <code>standard</code> <code>io1</code>
<code>description</code>	Description of the EMI
<code>hypervisor</code>	Hypervisor type of the image. Valid values: <code>ovm</code> <code>xen</code>
<code>image-id</code>	ID of the image

Filter	Description
image-type	Type of the image. Valid values: machine kernel ramdisk
is-public	Whether the image is public Valid values: true false
kernel-id	Kernel ID
manifest-location	Path to the image manifest
name	Name of the EMI
owner-alias	Account alias (for example, eucalyptus or self)
owner-id	Eucalyptus account ID of the image owner
platform	Enter windows if you have Windows-based EMIs. Otherwise leave blank.
product-code	Product code associated with the EMI
ramdisk-id	ID of the ramdisk
root-device-name	Root device name of the EMI (for example, /dev/sda1)
root-device-type	Root device type the EMI uses. Valid Values: ebs instance-store
state	State of the image. Valid values: available pending failed
tag-key	Key of a tag assigned to the resource you want to filter. This filter is independent of the tag-value filter and returns all resources assigned the tag key you use, regardless of the value. To filter on a specific key and value set, use the tag:key filter.
tag-value	Value of a tag assigned to the resource. This filter is independent of the tag-key filter and returns all resources assigned the tag value you use, regardless of the key. To filter on a specific key and value set, use the tag:key filter.
tag:key	Filters the results based on a specific tag/value combination

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.

Option	Description
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("IMAGE")
- Image ID
- Manifest path
- Account ID that registered the image
- Image status (available, pending, failed)
- Image visibility (public or private)
- Product codes, if any, attached to the instance
- Image architecture (i386 or x86_64)
- Image type (machine, kernel, or ramdisk)
- Kernel ID of the kernel (machine images only)
- RAM ID associated with the image (machine images only)
- Root device type (ebs or instance-store)
- Virtualization type (paravirtual or hvm)
- Output type identifier ("BLOCKDEVICEMAPPING") for EMIs that use one or more EBS volumes
- Any tags assigned to the image
- Hypervisor type (xen or kvm)

Example

```
euca-describe-images
IMAGE   eki-3E5B3B31
mah-bukkit/vmlinuz-2.6.28-11-generic.manifest.xml  00000000000001
available  public      x86_64  kernel      instance-store
IMAGE   emi-815A395B   mah-bukkit/ubuntu.9-04.x86-64.img.manifest.xml
790547641019  available  public      x86_64  machine eki-3E5B3B31
eri-32B338DC   instance-store
IMAGE   eri-32B338DC
mah-bukkit/initrd.img-2.6.28-11-generic.manifest.xml  00000000000001
available  public      x86_64  ramdisk    instance-store
```

euca-describe-instance-status

Show information about instance status and scheduled events.

Syntax

```
euca-describe-instance-status [--hide-healthy]
[--include-all-instances]
[--show-empty-fields] [-U URL]
[--region USER@REGION] [-I KEY_ID]
[-S KEY] [--security-token TOKEN]
```

```
[--filter name=value] [--debug]
[--debugger] [--version] [-h]
[instance_id [instance_id ...]]
```

Options

Option	Description	Required
instance_id	Limit results to the specified instance(s).	No
--hide-healthy	Hide instances where all status checks pass	No
--include-all-instances	Show all instances, not just those that are running.	No
--filter name=value	Restrict results to those that meet the specified filter criteria (see below).	No
-F, --filter name=value	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain instances. For example, you can use a filter to specify that you want to find instances launched with a specific status. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for an instance only if it matches at least one of the filter values that you specified.
- You can use multiple filters. Eucalyptus responds with the information for an instance only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `*eucalyptus?\` searches for the literal string `*eucalyptus?\`.

The following are the available filters for `euca-describe-instance-status`:

Filter	Description
availability-zone	Availability zone of the instance
event.code	Code identifying the type of event
event.description	Description of the event.
event.not-after	Event's latest possible end time
event.not-before	Event's earliest possible start time
instance-state-code	Numeric code identifying instance state
instance-state-name	Instance state
instance-status.status	Instance's status
instance-status.reachability	Instance's reachability status

Filter	Description
system-status.status	Instance's system status
system-status.reachability	Public DNS name of the instance.
group-id	Instance's system reachability status

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Examples

The following example shows the request and output for a simple command.

```
euca-describe-instance-status
INSTANCE i-65c77b9e one running 16 ok ok active
SYSTEMSTATUS reachability passed
INSTANCESTATUS reachability passed
```

euca-describe-instance-types

Shows information about instance types.

Syntax

```
euca-describe-instance-types instance_types [--by-zone] [--show-capacity]
```

Options

Option	Description	Required
<code>instance_type</code>	Instance type to describe	No
<code>--by-zone</code>	Show information for each availability zone separately	No
<code>--show-capacity</code>	Show information about instance capacity	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("INSTANCETYPE")
- Instance type name
- Number of CPUs
- Memory in MB
- Disk space in GB

Examples

The following example shows the request and output for a simple command.

```
euca-describe-instance-types
INSTANCETYPE Name      CPUs  Memory (MB)  Disk (GB)
INSTANCETYPE m1.small   1      256          5
INSTANCETYPE t1.micro   1      256          5
INSTANCETYPE m1.medium  1      512         10
INSTANCETYPE c1.medium  2      512         10
INSTANCETYPE m1.large   2      512         10
INSTANCETYPE m1.xlarge  2     1024         10
INSTANCETYPE c1.xlarge  2     2048         10
INSTANCETYPE m2.xlarge  2     2048         10
```

INSTANCETYPE	m3.xlarge	4	2048	15
INSTANCETYPE	m2.2xlarge	2	4096	30
INSTANCETYPE	m3.2xlarge	4	4096	30
INSTANCETYPE	cc1.4xlarge	8	3072	60
INSTANCETYPE	m2.4xlarge	8	4096	60
INSTANCETYPE	hi1.4xlarge	8	6144	120
INSTANCETYPE	cc2.8xlarge	16	6144	120
INSTANCETYPE	cg1.4xlarge	16	12288	200
INSTANCETYPE	cr1.8xlarge	16	16384	240
INSTANCETYPE	hs1.8xlarge	48	119808	24000

euca-describe-instances

Shows information about instances.

Syntax

```
euca-describe-instances instance_id [--filter "name=value"] ...]
```

Options

Option	Description	Required
<code>instance_id</code>	Instance ID to describe	No
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain instances. For example, you can use a filter to specify that you want to find instances launched with a specific keypair. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for an instance only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify instances launched with a specific keypair and use an EBS volume as the root device. Eucalyptus responds with the information for an instance only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-instances`:

Filter	Description
<code>architecture</code>	Instance architecture. Valid values: <code>i386</code> <code>x86_64</code>
<code>association.allocation-id</code>	(VPC only) Allocation ID bound to a network interface's elastic IP address.
<code>association.ip-owner-id</code>	(VPC only) ID of the owner of the elastic IP address associated with a network interface.

Filter	Description
association.public-ip	(VPC only) Address of the elastic IP address bound to a network interface.
availability-zone	The instance's availability zone.
block-device-mapping.attach-time	Attach time for an EBS volume mapped to the instance.
block-device-mapping.delete-on-termination	Whether the EBS volume is deleted on instance termination.
block-device-mapping.device-name	Device name (for example, /dev/sdh) for an EBS volume mapped to the image
block-device-mapping.status	Status of an EBS volume mapped to the instance. Valid values: attaching attached detaching detached
block-device-mapping.volume-id	ID of an EBS volume mapped to the instance.
dns-name	Public DNS name of the instance.
group-id	The security group the instance is in.
hypervisor	Hypervisor type of the instance. Valid values are ovm xen
image-id	ID of the image used to launch the instance.
instance-id	ID of the instance.
instance-lifecycle	Whether this is a spot instance. Valid values: true false
instance-state-code	Code identifying the state of the instance. Valid values: Valid values: 0 (pending) 16 (running) 32 (shutting-down) 48 (terminated) 64 (stopping) 80 (stopped)
instance-state-name	State of the instance. Valid Values: pending running shutting-down terminated stopping stopped
instance-type	Type of the instance (for example, m1.small)
ip-address	Public IP address of the instance.
kernel-id	Kernel ID.
key-name	Name of the key pair used when the instance was launched.
launch-index	When launching multiple instances at once, this is the index for the instance in the launch group .
launch-time	Time the instance was launched.
monitoring-state	Whether monitoring is enabled for the instance .
network-interface.addresses.association.owner-id	(VPC only) ID of the owner of the private IP address associated with a network interface. association.ip-

Filter	Description
network-interface.addresses.association.public-ip	(VPC only) ID of the association of an elastic IP address with a network interface.
network-interface.addresses.primary.private-ip	(VPC only) Indicates whether the IP address of the VPC network interface is the primary private IP address.
network-interface.addresses.private-ip-address	(VPC only) Network interface's private IP address.
network-interface.attachment.device-index	(VPC only) Device index to which a network interface is attached.
network-interface.attachment.attach-time	(VPC only) Time a network interface was attached to an instance.
network-interface.attachment.attachment-id	(VPC only) ID of a network interface's attachment.
network-interface.attachment.delete-on-termination	(VPC only) Indicates whether a network interface attachment is deleted when an instance is terminated.
network-interface.attachment.instance-owner-id	(VPC only) ID of the instance to which a network interface is attached.
network-interface.attachment.status	(VPC only) Network interface's attachment status.
network-interface.availability-zone	(VPC only) Network interface's availability zone.
network-interface.description	(VPC only) Description of a network interface.
network-interface.group-id	(VPC only) Network interface's security group ID.
network-interface.group-name	(VPC only) Network interface's security group name.
network-interface.mac-address	(VPC only) Network interface's hardware address.
network-interface.network-interface-id	(VPC only) ID of a network interface.
network-interface.owner-id	(VPC only) ID of a network interface's owner.

Filter	Description
<code>network-interface.private-dns-name</code>	(VPC only) Network interface's private DNS name.
<code>network-interface.requester-id</code>	(VPC only) Network interface's requester ID.
<code>network-interface.requester-managed</code>	(VPC only) Indicates whether the network interface is managed by the service.
<code>network-interface.source-destination-check</code>	(VPC only) Indicates whether source/destination checking is enabled for a network interface.
<code>network-interface.status</code>	(VPC only) Network interface's status.
<code>network-interface.subnet-id</code>	(VPC only) ID of a network interface's subnet.
<code>network-interface.vpc-id</code>	(VPC only) ID of a network interface's VPC.
<code>owner-id</code>	Account ID of the image owner.
<code>placement-group-name</code>	Name of the placement group that contains the instance.
<code>platform</code>	Use windows if you have Windows based AMIs, otherwise leave blank.
<code>private-dns-name</code>	Private DNS name of the instance.
<code>private-ip-address</code>	Private IP address of the instance.
<code>ramdisk-id</code>	The ramdisk ID.
<code>reason</code>	Reason for the instance's current state.
<code>reservation-id</code>	ID of the instance's reservation.
<code>root-device-name</code>	Root device name of the EMI (for example, <code>/dev/sda1</code>).
<code>root-device-type</code>	Root device type the EMI uses. Valid Values: <code>ebs</code> <code>instance-store</code>
<code>spot-instance-request-id</code>	ID of the spot instance request.
<code>state-reason-code</code>	Reason code for the state change.
<code>state-reason-message</code>	Message for the state change.
<code>subnet-id</code>	ID of the subnet the instance is in (VPC).
<code>tag-key</code>	Key of a tag assigned to the resource you want to filter. This filter is independent of the <code>tag-value</code> filter and returns all resources assigned the tag key you use, regardless of the value. To filter on a specific key and value set, use the <code>tag:key</code> filter.

Filter	Description
tag-value	Value of a tag assigned to the resource. This filter is independent of the tag-key filter and returns all resources assigned the tag value you use, regardless of the key. To filter on a specific key and value set, use the tag:key filter.
tag:key	Filters the results based on a specific tag/value combination
virtualization-type	Virtualization type of the instance. Valid values: paravirtual hvm
vpc-id	(VPC only) ID of the VPC containing the instance.

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("RESERVATION")
- Reservation ID
- Account ID
- Security group name
- Output type identifier ("INSTANCE")
- Instance ID
- EMI ID that the instance is based on
- Instance state
- Product codes attached to the instance
- Instance type
- Instance launch time
- Availability Zone
- Kernel ID

- RAM disk ID
- Public IP address
- Private IP address
- Type of root device (ebs or instance-store)
- Placement group the cluster instance is in
- Output type identifier ("BLOCKDEVICE") for each EBS volume the instance is using
- Block device name
- Volume ID
- Timestamp

Examples

The following example shows the request and output for a simple command.

```
euca-describe-instances
RESERVATION    r-1AE63E97    133764149866    admingroup
INSTANCE      i-1BD543F0    emi-EBD5387D    192.168.10.187    10.1.0.107
running      adminkey    0    m1.small    2012-02-15T17:24:52Z    PARTI00
eki-6DF93987    eri-4CEF36C4
```

euca-describe-keypairs

Shows information about key pairs.

Syntax

```
euca-describe-keypairs [ keypair_name ] [--filter "name=value"] ...]
```

Options

Option	Description	Required
keypair_name	Key pair name to describe	No
-F, --filter <i>name=value</i>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain keypairs. For example, you can use a filter to specify that you want to find keypairs that include the string `lampin` in their name. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a keypair only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify keypairs that include the string `lampin` in their name and that have a specific value in their fingerprint. Eucalyptus responds with the information for a keypair only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-keypairs`:

Filter	Description
fingerprint	Fingerprint of the key pair
key-name	Name of the keypair

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("KEYPAIR")
- Key pair name
- Private key fingerprint

Example

```
euca-describe-keypairs
KEYPAIR mykey 52:5f:e7:03:67:ad:b5:f3:65:4b:94:77:90:61:5f:1e:44:96:74:62
```

euca-describe-regions

Shows information about regions.

Syntax

```
euca-describe-regions [ region_name ] [--filter "name=value"] ...]
```

Options

Option	Description	Required
<code>region_name</code>	Region name to describe	No
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes only certain regions. You can also use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-regions`:

Filter	Description
<code>endpoint</code>	Endpoint of the region
<code>region-name</code>	Name of the region

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("REGION")
- Region name
- Service endpoint

Example

```
REGION eucalyptus http://86.75.30.9:8773/services/Eucalyptus
REGION walrus http://86.75.30.9:8773/services/Walrus
```

euca-describe-snapshots

Shows information about snapshots.

Syntax

```
euca-describe-snapshots [ snapshot_id ] [-o, owner ]
                        [-r restorable_by ] [-v] [--filter "name=value" ] ...]
```

Options

Option	Description	Required
snapshot_id	Snapshot ID to describe	No
-o, --owner <i>owner</i>	Returns snapshots owned by the specified owner. Multiple owners can be specified. Valid values: self account ID	No
-r, --restorable-by <i>user_id</i>	Account ID that can create volumes from the snapshot Valid values: self all account ID	No
-F, --filter <i>name=value</i>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain snapshots. For example, you can use a filter to specify that you want to find snapshots whose status is `pending`. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a snapshot only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can use a filter to specify that you want to find snapshots whose status is `pending` and have a specific tag. Eucalyptus responds with the information for a snapshot only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus\?\` searches for the literal string `*eucalyptus?\`.

The following are the available filters for `euca-describe-snapshots`:

Filter	Description
description	Description of the snapshot
owner-alias	Account alias (for example, eucalyptus or self) or Account ID that owns the snapshot.
owner-id	Account ID of the snapshot owner
progress	The progress of the snapshot, in percentage

Filter	Description
snapshot-id	The ID of the snapshot.
start-time	Time stamp when the snapshot was initiated
status	Status of the snapshot. Valid values: pending completed error
tag-key	Key of a tag assigned to the resource you want to filter. This filter is independent of the tag-value filter and returns all resources assigned the tag key you use, regardless of the value. To filter on a specific key and value set, use the tag:key filter.
tag-value	Value of a tag assigned to the resource. This filter is independent of the tag-key filter and returns all resources assigned the tag value you use, regardless of the key. To filter on a specific key and value set, use the tag:key filter.
tag:key	Filters the results based on a specific tag/value combination
volume-id	ID of the volume the snapshot is for
volume-size	The size of the volume, in GB

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("SNAPSHOT")
- Snapshot ID
- Volume ID
- Snapshot state
- Time stamp when snapshot initiated

- Percentage of completion
- Owner ID
- Volume size
- Description

Example

```
euca-describe-snapshots
SNAPSHOT    snap-5E313F37    vol-84B54112    completed
2012-01-01T00:00:00Z    100%
```

euca-describe-tags

Lists tags associated with your account.

Syntax

```
euca-describe-tags [--filter "name=value"] ...]
```

Options

Option	Description	Required
-F, --filter <i>name=value</i>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain tags. For example, you can use a filter to specify that you want to find tags for a specific resource type. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a volume only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can use a filter to specify that you want to find volumes whose status is `available` and have a specific tag. Eucalyptus responds with the information for a volume only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-volumes`:

Filter	Description
key	Tag key
resource-id	ID of the resource
resource-type	Resource type. Valid values: <code>customer-gateway</code> <code>dhcp-options</code> <code>image</code> <code>instance</code> <code>reserved-instances</code> <code>snapshot</code> <code>spot-instances-request</code> <code>subnet</code> <code>volume</code> <code>vpc</code> <code>vpn-connection</code> <code>vpn-gateway</code>
value	Tag value

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("TAG")
- Resource type
- Resource ID
- Tag key
- Tag value

Examples

The following example describes all your tags.

```
euca-describe-tags
TAG emi-1a2b3c4d image appserver
TAG emi-1a2b3c4d image stack dev
TAG i-5f4e3d2a instance appserver
TAG i-5f4e3d2a instance stack dev
TAG i-12345678 instance database_server
TAG i-12345678 instance stack test
```

The following example describes the tags for a resource with ID emi-1a2b3c4d.

```
euca-describe-tags --filter "resource-id=emi-1a2b3c4d"
TAG emi-1a2b3c4d image appserver
TAG emi-1a2b3c4d image stack dev
```

The following example describes the tags for all your instances.

```
euca-describe-tags --filter "resource-type=instance"
TAG i-5f4e3d2a instance appserver
TAG i-5f4e3d2a instance stack dev
TAG i-12345678 instance database_server
TAG i-12345678 instance stack test
```

The following example describes the tags for all your instances that have a tag with the key `appserver`.

```
ec2-describe-tags --filter "resource-type=instance" --filter "key=appserver"
TAG i-5f4e3d2a instance appserver
```

The following example describes the tags for all your instances that have a tag with the key `stack` and a value of either `dev` or `test`.

```
euca-describe-tags --filter "resource-type=instance" --filter "key=stack" --
filter
    "value=dev" --filter "value=test"
TAG i-5f4e3d2a instance stack test
TAG i-12345678 instance stack dev
```

euca-describe-volumes

Shows information about volumes.

Syntax

```
euca-describe-volumes [ volume_id ] [-v] [[--filter "name=value"] ...]
```

Options

Option	Description	Required
<code>volume_id</code>	Volume ID to describe	No
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain volumes. For example, you can use a filter to specify that you want to find volumes whose status is `available`. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a volume only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can use a filter to specify that you want to find volumes whose status is `available` and have a specific tag. Eucalyptus responds with the information for a volume only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-volumes`:

Filter	Description
<code>attachment.attachment-time</code>	Time stamp when the attachment initiated
<code>attachment.delete-on-termination</code>	Whether the volume will be deleted on instance termination.
<code>attachment.device</code>	How the volume is exposed to the instance (for example, <code>/dev/sda1</code>)

Filter	Description
<code>attachment.instance-id</code>	ID of the instance the volume is attached to
<code>attachment.status</code>	Attachment state. Valid values: <code>attaching</code> <code>attached</code> <code>detaching</code> <code>detached</code>
<code>availability-zone</code>	Availability Zone in which the volume was created
<code>create-time</code>	Time stamp when the volume was created
<code>size</code>	Size of the volume, in GB (for example, 20)
<code>snapshot-id</code>	Snapshot from which the volume was created
<code>status</code>	Status of the volume. Valid values: <code>pending</code> <code>completed</code> <code>error</code>
<code>tag-key</code>	Key of a tag assigned to the resource you want to filter. This filter is independent of the <code>tag-value</code> filter and returns all resources assigned the tag key you use, regardless of the value. To filter on a specific key and value set, use the <code>tag:key</code> filter.
<code>tag-value</code>	Value of a tag assigned to the resource. This filter is independent of the <code>tag-key</code> filter and returns all resources assigned the tag value you use, regardless of the key. To filter on a specific key and value set, use the <code>tag:key</code> filter.
<code>tag:key</code>	Filters the results based on a specific tag/value combination
<code>volume-id</code>	ID of the volume the snapshot is for

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("VOLUME")
- Volume ID
- Volume size, in GiBs
- Snapshot the volume was created from, if applicable
- Availability zone that the volume was launched in
- Volume state
- Time stamp when volume creation initiated

Example

```
euca-describe-volumes
VOLUME vol-84B54112    5    zone00    available    2012-01-01T00:00:00.000Z
```

euca-detach-volume

Detaches a volume from an instance.

Syntax

```
euca-detach-volume volume_id [-i instance_id ][-d device ][-f ]
```

Options

Option	Description	Required
<i>volume_id</i>	Volume ID to be detached	Yes
-i, --instance <i>instance_id</i>	Instance ID	No
-d, --device <i>device</i>	Device name	No
-f, --force	Forces detachment if the previous detachment did not occur cleanly. Use only as a last resort to detach a volume from a failed instance. Perform file system check and repair procedures if you use this option.	

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.

Option	Description
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("VOLUME")
- Volume ID

Example

```
euca-detach-volume vol-639C3E6C
VOLUME vol-639C3E6C
```

euca-disassociate-address

Disassociate an elastic IP address from an instance.

Syntax

```
euca-disassociate-address ip
```

Options

Option	Description	Required
<code>ip</code>	Elastic IP address to disassociate	

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.

Option	Description
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("ADDRESS")
- IP address

Example

```
euca-disassociate-address 86.75.30.9
ADDRESS 86.75.30.9
```

euca-download-bundle

Download the specified bundles from object storage.

Syntax

```
euca-download-bundle -b bucket [-m manifest_path
    ][-p prefix ][-d directory ]
```

Options

Option	Description	Required
-b, --bucket <i>bucket</i>	Name of the bucket where the bundle is located.	Yes
-m, --manifest <i>manifest</i>	The manifest filename (without the path). We recommend you specify either the manifest (option -m), or the filename prefix (option -p).	Conditional
-p, --prefix <i>emi_prefix</i>	The filename prefix for the bundled EMI files	Conditional
-d, --directory <i>directory</i>	The directory where the downloaded bundle is saved. This directory must exist. Default: /tmp	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.

Option	Description
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns status messages that indicate the various stages of the download process.

Example

```
euca-download-bundle -b mah-bukkit -m myimage.img.manifest.xml
Downloading myimage.img.manifest.xml
Downloading myimage.img.part.00
Downloading myimage.img.part.01
Downloading myimage.img.part.02
Downloading myimage.img.part.03
```

euca-download-and-unbundle

Download and unbundle a bundled image from the cloud.

Syntax

```
euca-download-and-unbundle -b bucket_name [/PREFIX]
[-d (file | directory)] [-k private_key]
[--progress | --no-progress]
(-m manifest | -p manifest | --local-manifest filename)
[-U URL] [--region user@region] [-I key_ID]
[-S key] [--security-token token] [--debug]
[--debugger] [--version] [-h]
```

Options

Option	Description	Required
-b bucket_name [/PREFIX]	The name of the bucket that contains the bundle, with an optional path prefix.	Yes
-d (file directory)	Destination for the unbundled image: Default: the current directory.	No
-k private_key, --privatekey private_key	The name of the file containing the private key to be used to decrypt the bundle. This must match the certificate used when bundling the image.	No

Option	Description	Required
<code>--progress</code>	Show a progress bar during command execution. This is the default when this command is run interactively.	No
<code>--no-progress</code>	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No
<code>--productcodes</code> <i>code1</i> [, <i>code2</i> , ...]	Comma-delimited list of product codes.	No
<code>--progress</code>	Show a progress bar during command execution. This is the default when this command is run interactively.	No
<code>--no-progress</code>	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No
<code>-m</code> manifest , <code>--manifest</code> manifest	File name of the manifest, not including any path that may be specified with the <code>-b</code> parameter.	No
<code>-p</code> manifest , <code>--prefix</code> manifest	Portion of the manifest's file name that precedes ".manifest.xml"	No
<code>--local-manifest</code> filename	Specifies a manifest to use instead of the manifest supplied by the server.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region</code> <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url</code> <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id</code> <i>key_id</i>	User's access key ID.
<code>-S, --secret-key</code> <i>secret_key</i>	User's secret key.
<code>--security-token</code> <i>token</i>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

euca-fingerprint-key

Show the fingerprint of a private key as it would appear in the output of `euca-fingerprint-key`.

Syntax

```
euca-fingerprint-key filename
```

Options

Option	Description	Required
<i>filename</i>	File containing the private key.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Example

```
euca-fingerprint-key my-private-key.pem
17:db:9a:f4:33:1c:ff:6a:b2:ae:69:0d:22:2c:fc:a9:44:6e:22:f8
```

euca-get-console-output

Prints console output from a running instance. This command is not supported on all hypervisors. This works if you are using KVM.

Syntax

```
euca-get-console-output instance_id [-r]
```

Options

Option	Description	Required
<i>instance_id</i>	Instance ID that you want to see the console output for	Yes

Option	Description	Required
<code>-r, --raw-console-output</code>	Display output without escaping control characters	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Instance ID
- Timestamp indicating the time of the last update
- Console output for the instance

Example

```
euca-get-console-output i-12623E16
i-12623E16
2012-01-01T00:00:00.000Z
...
```

euca-get-password

Retrieves and decrypts the administrator password for a Windows instance.

Syntax

```
euca-get-password instance_id -k key_file
```

Options

Option	Description	Required
<code>-k, --priv-launch-key <i>key_file</i></code>	The file that contains the private key used to launch the instance	Yes
<code><i>instance_id</i></code>	Windows instance ID	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the Windows administrator password.

Example

```
euca-get-password -k mykey i-12623E16
YxL8y3me
```

euca-get-password-data

Gets encoded version of the password, which you then need to decrypt using the private key.

Syntax

```
euca-get-password-data instance_id
```

Options

Option	Description	Required
<i>instance_id</i>	ID of the Windows instance	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the encoded version of the password.

Example

```
euca-get-password-data i-12623E16
cGbkqqXlxcDTaMTYZMaQ77/1w6Pnzd7mkczNeBXde16T4SHW71KKCTYWrwE9v8VXCefvW8P5HTScNVNs
Uv4zEXpAkJ/jxToITVvUEyazGwNG0vRk8t
+nVgLaCJUksf5sxz0c0oiVUK5hiFHqpylli9wXLGY7TRc
XGdyFGdY2URLV5luT9SS9yF2R9yIGRiq061ptdmPF8PQ0unpKKGxC2SqKnhsoEtrLiGXDAMMS/
JCvCK8
ZuCnjMSph1sPYoNlUJT3NGwXvoNJEzedrRNLY8mdFBphVxsimWSv5XDURckvfJa1JwgFvPrvAoAeN8MP
tmV9Gjz8I6CWznomN6Wmgw==
```

euca-import-keypair

Import a public RSA key as a new key pair for Eucalyptus.

Syntax

```
euca-import-keypair -f file KEYPAIR
```

Options

Options	Description	Required
-f FILE	Name of the file containing the public key to import	Yes
KEYPAIR	Unique name for the new keypair.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Example

```
euca-import-keypair -f /path/to/keypair mykey
```

euca-import-instance

Import an instance into the cloud.

Syntax

```
euca-import-instance -t instance_type -f format -a architecture
    -p {Windows, Linux} (-b bucket | --manifest-url URL)
    [--prefix prefix] [-x days] [--no-upload]
    [-d description] [-g group] [-z zone] [-s GBs]
    [--image-size bytes]
    [--user-data data | --user-data-file filename]
    [--subnet subnet] [--private-ip-address address]
    [--monitor]
    [--instance-initiated-shutdown-behavior {stop, terminate}]
    [--key keypairname] filename
```

Options

Options	Description	Required
<code>filename</code>	The file containing the disk image to import.	Yes
<code>-t type, --instance-type type</code>	The type of instance to import.	Yes
<code>-f format, --format format</code>	The format of the image. Valid values: raw, or vhd	Yes
<code>-a architecture, --arch architecture</code>	Architecture of the new instance. Valid values: i386,x86_64,armhf,ppc, or ppc64.	Yes
<code>-p platform, --platform platform</code>	The operating system for the instance. Valid values: Windows or Linux	Yes
<code>-b bucket, --bucket bucket</code>	Bucket to upload volume to.	Yes
<code>--manifest-url URL</code>	A pre-signed URL that points to the import manifest to use.	Yes
<code>--prefix prefix</code>	The prefix to add to the names of the volume parts as they are uploaded.	No
<code>-x days, --expires days</code>	The amount of time, in days, that the import manifest should remain valid. Default: 30 days	Conditional
<code>--no-upload</code>	Start the import process, but do not actually upload the volume	No
<code>--description</code>	Description of the import task.	No
<code>-g group, --group group</code>	Name of the security group to create the instance in.	No
<code>-z zone, --zone zone</code>	Name of the zone to create the instance in.	No
<code>-s gb, --size gb</code>	Size of the volume to import to, in gigabytes.	No
<code>--image-size size</code>	The size of the image. Required for non-raw files.	Conditional
<code>--user-data data</code>	User data to supply to the instance.	No
<code>--user-data-file file</code>	File containing user data to supply to the instance.	No
<code>--subnet subnet</code>	[VPC only] Subnet in which to create the instance's network interface.	No
<code>--private-ip-address address</code>	[VPC only] Assign the specified primary private IP address to the instance's interface.	No
<code>--monitor</code>	Enable detailed monitoring for the instance.	No

Options	Description	Required
<code>--instance-initiated-shutdown-behavior <i>behavior</i></code>	Indicates whether to stop or terminate the instance when it's shut down. Valid values: <code>stop</code> , <code>terminate</code> Default: <code>stop</code>	No
<code>--key <i>keypairname</i></code>	[Eucalyptus only] The name of the key pair to use when running the instance.	No
<code>-o <i>key</i>, --owner-akid <i>key</i></code>	The access key to use for the object storage service. Default: same as that for the compute service.	No
<code>-w <i>key</i>, --owner-sak <i>key</i></code>	The secret key to use for the object storage service. Default: same as that for the compute service.	No
<code>--progress</code>	Show a progress bar during command execution. This is the default when this command is run interactively.	No
<code>--no-progress</code>	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Example

```
euca-import-instance myimagefile -p Linux -f raw -t m1.large -a x86_64 -b my-bukkit
```

euca-install-image

Bundle, upload and register an image into the cloud.

Syntax

```
euca-install-image -n name [--description description]
[--max-pending-parts max_pending_parts]
[--virtualization-type {paravirtual,hvm}]
[--platform windows] [--ec2-url EC2_URL] -i filename
[-p prefix] [-d dir] -r
  {i386,x86_64,armhf,ppc,ppc64} [-k filename] [-c filename]
[--ec2cert filename] [-u account] [--kernel image_id]
[--ramdisk image]
[-B virtual1=device1,virtual2=device2,...]
[--productcodes code1,code2,...]
[--image-size image_size] -b bucket[/prefix]
[--acl {public-read,aws-exec-read,ec2-bundle-read}]
[--upload-policy policy | --upload-policy-file policy_file]
[--upload-policy-signature signature]
[--location location] [--retry]
[--progress | --no-progress]
```

Options

Options	Description	Required
-n <i>name</i>	The name of the new image.	Yes
--description	The description of the new image.	No
--max-pending-parts <i>max_parts</i>	Pause the bundling process when more than this number of parts are waiting to be uploaded.	No
--virtualization-type <i>type</i>	Virtualization type for the new image. Valid values: paravirtual, hvm	No
--platform-windows	[Privileged] Indicates the new image is based on Windows.	No
--ec2-url	Compute service endpoint URL	No
-i <i>file</i> , --image <i>file</i>	The file containing the image to bundle.	Yes
-p <i>prefix</i> , --prefix <i>prefix</i>	The file name prefix to give the bundle image files. Required when bundling stdin; otherwise defaults to the image's file name.	Conditional
-d <i>directory</i> , --destination <i>directory</i>	Directory where the bundle image files go. Eucalyptus recommends that you include this option where allowed. This is the directory specified by TMPDIR, TEMP, or TMP environment variables. Default: /var/tmp	No
-r <i>architecture</i> , --arch <i>architecture</i>	Target architecture for the image. Default: x86_64 Valid values: i386 x86_64 armhf ppc ppc64	Yes
-k <i>file</i> , --privatekey <i>file</i>	File containing your private key to sign the bundle's manifest with. This private key will also be required to unbundle the image in the future.	No

Options	Description	Required
<code>-c file, --cert file</code>	File containing your X.509 certificate.	No
<code>--ec2cert file</code>	File containing your cloud's X.509 certificate.	No
<code>-u account, --user account</code>	12-digit account ID of the person who is bundling the image.	No
<code>--kernel image</code>	ID of the kernel image to associate with this machine image.	No
<code>--ramdisk image</code>	ID of the ramdisk image to associate with this machine image.	No
<code>-B, --block-device-mapping</code>	Default block device mapping for the image. The format of the mapping is a comma-separated list of key=value pairs.	No
<code>-\nproductcodescode1 [, code2, ...]</code>	Comma-delimited list of product codes.	No
<code>--image-size size</code>	The size of the image. Required when reading from <code>stdin</code> .	Conditional
<code>-b bucket[/PREFIX], --bucket bucket[/PREFIX]</code>	Bucket to upload the image bundle to.	Yes
<code>--acl policy</code>	ACL policy to apply to the bucket. Default: <code>aws-exec-read</code> Valid values: <code>public-read,aws-exec-read,ec2-bundle-read</code>	Yes
<code>--upload-policy policy</code>	Upload policy to use for authorization.	No
<code>--upload-policy-file file</code>	File containing an upload policy to use for authorization.	No
<code>--upload-policy-signature policy</code>	signature for the upload policy. Required when an upload policy is used.	Conditional
<code>--location location</code>	Location constraint of the destination bucket. Default: obtained from <code>s3-location-constraint</code> in configuration, or otherwise none.	Conditional
<code>--retry</code>	Retry failed uploads up to five times.	No
<code>--progress</code>	Show a progress bar during command execution. This is the default when this command is run interactively.	No
<code>--no-progress</code>	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".

Option	Description
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Example

```
euca-install-image -n 'My image' -r x86_64 -b my-bukkit -i my-image.raw
```

euca-modify-image-attribute

Modifies an attribute of an Eucalyptus Machine Image (EMI).

Syntax

```
euca-modify-image-attribute image_id [ -l ] [ -p product_code ] [ -a entity ] [ -r entity ]
```

Options

Option	Description	Required
<i>image_id</i>	Unique identifier for the image that you want to modify the attributes of	Yes
<code>-l, --launch-permission</code>	Used with the <code>--add</code> or <code>--remove</code> option to grant or revoke launch permissions	Yes
<code>-a, --add entity</code>	Adds a launch permission for the specified account or for all accounts. Valid Values: <code>account identifier all</code>	Yes
<code>-r, --remove entity</code>	Removes a launch permission for the specified account or for all users. Valid Values: <code>account identifier all</code>	Yes
<code>-p, --product-code code</code>	Product code to add to the specified EMI. Once you add a product code to an EMI, it can't be removed	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("IMAGE")
- Image ID

Example

The following example makes the EMI public, so that all accounts can launch it.

```
euca-modify-image-attribute -l -a all emi-15A1386E
IMAGE    emi-15A1386E
```

The following example denies launch permission for a specific account.

```
euca-modify-image-attribute -l -r 790547641019 emi-15A1386E
IMAGE    emi-15A1386E
```

euca-modify-instance-attribute

Modify an attribute of the specified instance.

Syntax

```
euca-modify-instance-attribute [-b device:::(true|false)]
[--disable-api-termination {true,false}]
[--ebs-optimized {true,false}] [-g group]
[--instance-initiated-shutdown-behavior
{stop,terminate}] [-t instancetype]
[--kernel image] [--ramdisk image]
[--source-dest-check {true,false}]
[--sriov simple] [--user-data data]
```

```
[--user-data-file filename)] instance_id
```

Options

Options	Description	Required
<i>instance_id</i>	The ID of the instance to modify.	Yes
<code>-b device>::{true false}, --block-device-mapping device>::{true false}</code>	Change whether a volume attached to the instance will be deleted upon the instance's termination.	No
<code>--disable-api-termination {true false}</code>	Prevent API calls from terminating the instance(s).	No
<code>--ebs-optimized {true false}</code>	Change whether or not the instance should be optimized for EBS I/O.	No
<code>-g, --group group</code>	Security group to run the instance in	No
<code>-t, --instance-type</code>	Instance type to run. Valid values: m1.small t1.micro m1.medium m1.large c1.medium m1.xlarge c1.xlarge m2.xlarge m3.xlarge cc1.4xlarge m2.2xlarge m3.2xlarge m2.4xlarge hi1.4xlarge cc2.8xlarge cg1.4xlarge cr1.8xlarge hs1.8xlarge	No
<code>--kernel</code>	Kernel ID to be used	No
<code>--ramdisk</code>	Ramdisk ID to be used	No
<code>--source-dest-check {true false}</code>	Change whether source/destination address checking is enabled	No
<code>--sriov simple</code>	Enable enhanced networking for the instance and its descendants.	No
<code>--instance-initiated-shutdown-behavior behavior</code>	Indicates whether to stop or terminate the instance when it's shut down. Valid values: stop, terminate Default: stop	No
<code>--user-data user_data</code>	User data to pass to the instance.	No
<code>--user-data-file file</code>	File containing user data to supply to the instance.	No
<code>-B, --block-device-mapping</code>	Default block device mapping for the image. The format of the mapping is a comma-separated list of key=value pairs.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".

Option	Description
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Example

```
euca-modify-instance-attribute myinstanceid --disable-api-termination true -g mygroupname
```

euca-modify-instance-type

Modifies an instance type definition. This command is specific to Eucalyptus, and can only be run by a Eucalyptus cloud administrator.

Syntax

```
euca-modify-instance-type instance_type
[-c count] [-d disk_space] [-m ram_amount]
[--reset][--show-empty-fields]
```

Options

Option	Description	Required
<i>instance_type</i>	Name of the instance to modify	Yes
<code>-c, --count</code>	Number of virtual CPUs to allocate to each instance	No
<code>-d, --disk disk_space</code>	Amount of instance storage to allocate to each instance, in gigabytes	No
<code>-m, --memory entity</code>	Amount of RAM to allocate to each instance	No
<code>--reset</code>	Reset the instance type to its default configuration.	No
<code>--show-empty-fields</code>	Display empty values as "(nil)"	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("INSTANCETYPE")
- Instance type name
- Number of CPUs
- Memory in MB
- Disk space in GB

Example

The following example changes the m1.medium instance type so that it has 16 GB of disk space:

```
euca-modify-instance-type m1.medium --disk 16 --show-empty-fields
INSTANCETYPE m1.medium 1 512 16
```

euca-monitor-instances

Enables monitoring for running instances.

Syntax

```
euca-monitor-instances instance_id [instance_id...]
```

Options

Option	Description	Required
<i>instance_id</i> [<i>instance_id...</i>]	Unique identifier for instance to monitor	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

This command returns a table that contains the following information:

- The instance ID
- The monitoring state

Example

The following example enables monitoring for instances i-43a4412a and i-23a3397d.

```
euca-monitor-instances i-43a4412a i-23a3397d
i-43a4412a monitoring-pending
i-23a3397d monitoring-pending
```

euca-reboot-instances

Reboots specified instances.

Syntax

```
euca-reboot-instances instance_id [instance_id ...]
```

Options

Option	Description	Required
<code>instance_id</code>	Unique identifier for instance to reboot	At least 1 required

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("INSTANCE")
- Instance ID

Example

```
euca-reboot-instances i-12623E16
INSTANCE    i-12623E16
```

euca-register

Registers a manifest for use with the cloud. Note that the registered image by default is set to private. To make publicly available, use the `euca-modify-image-attribute` and set the `--add` value to `all`.

Syntax

```
euca-register [manifest] -n name [-d description ]
  [-a architecture ] [--kernel kernel ] [--ramdisk ramdisk ]
  [--root-device-name root_device_name ] [-b block_device_mapping ]
  [-s snapshot ] [--virtualization-type type]
```

Options

Option	Description	Required
<i>manifest</i>	Path to the uploaded image (bucket/manifest). Required if you are registering an S3-based image.	Conditional

Option	Description	Required
<code>-n, --name</code>	Name of the image. Constraints: 3-128 alphanumeric characters, parenthesis (), commas (,), slashes (/), dashes (-), or underscores(_)	Yes
<code>-d, --description <i>description</i></code>	Description of the image Constraints: Up to 255 characters.	No
<code>-a, --architecture <i>architecture</i></code>	The architecture of the image Valid Values: <code>i386</code> <code>x86_64</code>	No
<code>--kernel</code>	Kernel ID associated with the image	No
<code>--ramdisk</code>	Ramdisk ID associated with the image	No
<code>--root-device-name <i>name</i></code>	Root device name (for example, <code>/dev/sda1</code> , or <code>xvda</code>)	No
<code>-b, --block-device-mapping <i>mapping</i></code>	Block device mapping for the instance. This is passed in the form of <code><devicename>=<blockdevice></code> , where: <code>devicename</code> is the device name of the physical device on the instance to map and <code>blockdevice</code> is one of the following values: <code>none</code>: Use this value to suppress existing mapping on the specified image for this device. For example: <code>/dev/sdc=none</code> <code>ephemeral[0..3]</code>: Use this value to indicate that an instance local storage device should be mapped to this device. For example: <code>/dev/sdc=ephemeral0</code> <code>[snapshot-id]:[size]:[delete-on-termination (true false)]</code>: Use this value to map a device to an existing EBS-backed volume, and to specify whether the EBS volume should be deleted on termination. This value defaults to <code>true</code>. To specify a new EBS-backed volume, skip the snapshot ID and pass in a volume size instead. For example: <code>/dev/sdb=:20</code>.	No
<code>-s, --snapshot <i>snapshot</i></code>	EBS snapshot ID to use as the root device	No
<code>--virtualization-type <i>type</i></code>	The virtualization type for the new image. Valid values: <code>paravirtual</code> <code>hvm</code> Note: You should always explicitly declare the instance type of a bundle created with <code>euca-bundle-instance</code> as an HVM type using <code>--virtualization-type</code> parameter.	No
<code>--platform <i>windows</i></code>	[Privileged] Indicates that the new image is a Windows image.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.

Option	Description
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("IMAGE")
- Image ID
-

Example

```
euca-register -a 1386 --description 'My new image' --name 'myimage'
mah-bukkit/myimage.img.manifest.xml
IMAGE emi-15A1386E
```

euca-release-address

Releases an elastic IP address that you allocated.

Syntax

```
euca-release-address ip_address [-a allocation_ID ]
```

Options

Option	Description	Required
<code>ip_address</code>	The elastic IP address to release	Yes
<code>-a, --allocation-id allocation_ID</code>	(VPC only) Allocation ID for the address to release.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".

Option	Description
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("ADDRESS")
- Elastic IP address

Example

```
euca-release-address 86.75.30.9
ADDRESS 86.75.30.9
```

euca-reset-image-attribute

Reset attributes of an image.

Syntax

```
euca-reset-image-attribute image_id [-l]
```

Options

Option	Description	Required
<code>image_id</code>	Image ID that you want to reset the attributes for.	Yes
<code>-l, --launch-permission</code>	Reset launch permissions	

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".

Option	Description
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("IMAGE")
- Image ID

Example

The following example resets launch permissions for an image.

```
euca-reset-image-attribute -l emi-15A1386E
IMAGE emi-15A1386E
```

euca-resume-import

Perform the upload step of an import task.

Syntax

```
euca-resume-import -t task_id [-x days]
```

Options

Option	Description	Required
filename	The file containing the disk image to import.	Yes
<code>-t task, --task task</code>	ID of the import you want to resume.	Yes
<code>-x days, --expires days</code>	The amount of time, in days, that the import manifest should remain valid. This parameter has no effect for import tasks whose manifests have already been uploaded to object storage. Default: 30 days	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Example

The following example resets launch permissions for an image.

```
euca-resume-import mydiskimage -t 12314123
```

euca-revoke

Removes a rule from a security group.

Syntax

```
euca-revoke group_name [--egress] [-P {tcp,udp} -p port_range] [-s cidr_range]
```

```
euca-revoke group_name [--egress] [-P icmp -t type:code] [-s cidr_range]
```

Options

Option	Description	Required
<code>group_name</code>	Name of the security group to add the rule to.	Yes
<code>--egress</code>	(VPC only) Manage an egress rule, which controls traffic leaving the group. Default: If this option is not specified, the rule is an ingress rule (applies to traffic entering the group).	No

Option	Description	Required
-P, --protocol <i>protocol</i> <i>protocol_number</i>	IP protocol name or number. Valid values: tcp udp icmp -1/all Note: You can specify arbitrary <u>IANA-assigned protocol numbers</u> as well as the special values "all" and "-1", which refer to all network traffic, in VPC security groups. As a convenience, if a protocol is specified by name euca-authorize and euca-revoke will consult /etc/protocols to discover its number.	No
-p <i>port_range</i>	Specifies the range of ports to allow for TCP and UDP. Not valid for ICMP. Valid values: Single integer or range (min-max). Use -1 to specify all ports.	Conditional
-t, --icmp-type-code	ICMP type and code specified as "type:code". Only works if you specify ICMP as the protocol.	Conditional
-o, --source-group <i>source_group</i>	(Non-VPC only) Group from which traffic is authorized by the rule. Every instance in the security group is allowed to pass traffic.	No
-u, --source-group-user <i>source_group_user</i>	ID of the security group user you name in the -o parameter	No
-s, --source-subnet <i>source_subnet</i>	Addresses to apply the rule to Default: 0.0.0.0/0	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("GROUP", "PERMISSION")
- Group name
- Rule type (EC2 only supports an ALLOW rule)
- Protocol
- Port range start
- Port range end

Example

```
euca-revoke default -P tcp -p 80 -s 0.0.0.0/0
```

```
GROUP default
```

```
PERMISSION default ALLOWS tcp 80 80 FROM CIDR 0.0.0.0/0
```

```
euca-revoke -P tcp -p 6697-7000 -s 1.2.3.0/24 mygroup
```

```
GROUP mygroup
```

```
PERMISSION mygroup ALLOWS tcp 6697 7000 FROM CIDR 1.2.3.0/24
```

```
euca-revoke -P icmp -t 0:0 -o othergroup -u 1234567890 mygroup
```

```
GROUP mygroup
```

```
PERMISSION mygroup ALLOWS icmp USER 1234567890 GRPNAME othergroup
FROM CIDR 0.0.0.0/0
```

euca-run-instances

Runs instances of the specified machine image.

Syntax

```
euca-run-instances image_id [-n count] [-g group_name ]
[-k keypair] [-d user_data ] [-f user_data_file]
[-t instance_type] [--kernel kernel] [--ramdisk ramdisk ]
[-b block_device_mapping] [--monitor] [-z zone ]
[--disable-api-termination]
[--instance-initiated-shutdown-behavior value]
[--placement-group group_name]
[--tenancy value] [--client-token token_value] [-s subnet_value]
[--associate-public-ip-address value]
[--private-ip-address address] [--secondary-private-ip-address address]
[--secondary-private-ip-address-count count] [-a interface]
[-p IAM_profile] [--ebs-optimized]
```

Options

Option	Description	Require
<i>image_id</i>	ID of the image to run.	Yes
<i>-n, --instance-count min[-max]</i>	Number of instances to run. If this is specified as a range (min-max), Eucalyptus will try to run the maximum number, but no fewer than the minimum number.	No
<i>-g, --group group</i>	Security group to run the instance in.	No
<i>-k, --key keypair</i>	Name of a key pair. Not necessary to launch an instance as <i>cloud-init</i> is always executed if it exists inside an image.	No
<i>-d, --user-data user_data</i>	User data to pass to the instance.	No

Option	Description	Require
<code>--user-data-force <i>user_data</i></code>	Same as <code>--user-data</code> , but without checking if a file by that name already exists.	No
<code>-f, --user-data-file <i>user_data_file</i></code>	File containing user data to pass to the instance.	No
<code>--addressing <i>user_data_file</i></code>	(Eucalyptus only) Addressing scheme to use when launching the instance. Use <code>private</code> to run an instance with no public address. Valid values: <code>public</code> <code>private</code>	No
<code>-t, --instance-type</code>	Instance type to run. Valid values: <code>m1.small</code> <code>t1.micro</code> <code>m1.medium</code> <code>m1.large</code> <code>c1.medium</code> <code>m1.xlarge</code> <code>c1.xlarge</code> <code>m2.xlarge</code> <code>m3.xlarge</code> <code>cc1.4xlarge</code> <code>m2.2xlarge</code> <code>m3.2xlarge</code> <code>m2.4xlarge</code> <code>hi1.4xlarge</code> <code>cc2.8xlarge</code> <code>cg1.4xlarge</code> <code>cr1.8xlarge</code> <code>hs1.8xlarge</code>	No
<code>--kernel</code>	Kernel ID to be used.	No
<code>--ramdisk</code>	Ramdisk ID to be used.	No
<code>-b, --block-device-mapping</code>	Block device mapping for the instance. This is passed in the form of <code><devicename>=<blockdevice></code> , where: <code>devicename</code> is the device name of the physical device on the instance to map and <code>blockdevice</code> is one of the following values: <code>none</code>: Use this value to suppress existing mapping on the specified image for this device. For example: <code>/dev/sdc=none</code> <code>ephemeral[0..3]</code>: Use this value to indicate that an instance local storage device should be mapped to this device. For example: <code>/dev/sdc=ephemeral0</code> <code>[snapshot-id]:[size]:[delete-on-termination (true false)]</code>: Use this value to map a device to an existing EBS-backed volume, and to specify whether the EBS volume should be deleted on termination. This value defaults to <code>true</code>. To specify a new EBS-backed volume, skip the snapshot ID and pass in a volume size instead. For example: <code>/dev/sdb=:20</code>.	No
<code>-m, --monitor</code>	Enable monitoring for the instance. Boolean value. Defaults to Disabled.	No
<code>--disable-api-termination</code>	Prevent API calls from terminating the instance(s).	No
<code>--instance-initiated-shutdown-behavior value</code>	Indicates whether to stop or terminate EBS-backed instances upon shutdown. Valid values: <code>stop</code> (default) <code>terminate</code>	No
<code>--placement-group <i>group_name</i></code>	Specifies the placement group in which to launch the instance.	No

Option	Description	Require
<code>--tenancy value</code>	(VPC only) Indicates the type of tenancy for the instance. A value of dedicated indicates that the instance should run on single-tenant hardware. Valid values: default dedicated	No
<code>--client-token token_value</code>	Unique identifier to ensure request idempotency.	No
<code>-s, --subnet subnet_value</code>	(VPC only) Subnet for the instance's network interface.	No
<code>--associate-public-ip-address value</code>	(VPC only) Whether or not to assign public IP addresses to the new instances. This overrides the subnet's settings for whether or not to assign them by default. If you don't want a public IP address, set it to false ; and note that you need to also specify the <code>--subnet</code> option. Valid values: true false	No
<code>--private-ip-address address</code>	(VPC only) Assign the specified primary private IP address to an instance's interface.	No
<code>--secondary-private-ip-address address</code>	(VPC only) Assign the specified secondary private IP address to an instance's network interface. Use this option multiple times to add additional addresses.	No
<code>--secondary-private-ip-address-count count</code>	(VPC only) Automatically assign a specific number of secondary private IP addresses to an instance's network interface.	No
<code>-a, --network-interface interface</code>	(VPC only) Add the specified network interface to the new instance. If the interface already exists, supply its ID and a numeric index for it, separated by ":", in the form "eni-NNNNNNNN:INDEX". To create a new interface, supply a numeric index and subnet ID for it, along with (in order) an optional description, a primary private IP address, a list of security group IDs to associate with the interface, whether to delete the interface upon instance termination ("true" or "false"), a number of secondary private IP addresses to create automatically, and a list of secondary private IP addresses to assign to the interface, separated by ":", in the form: : INDEX: SUBNET: [DESCRIPTION]: [PRIV_IP]: [GROUP1, GROUP2, ...]: [true false]: [SEC_IP_COUNT : SEC_IP1, SEC_IP2, ...]. You cannot specify both. This option may be used multiple times. Each adds another network interface.	No
<code>-p, --iam-profile IAM_profile</code>	The name or ARN of the IAM instance profile to associate with the new instance(s).	No
<code>--ebs-optimized</code>	Optimize the new instance(s) for EBS I/O.	No
<code>-z, --availability-zone zone</code>	Availability zone to run the instance in.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("RESERVATION")
- Instance ID that uniquely identifies each running instance
- EMI ID of the image on which the instance(s) are based
- Instance state. This is usually pending, which indicates that the instance(s) are preparing to launch
- Key pair name (if a key pair was associated with the instance at launch)
- Product code (if applicable)
- Instance type
- Instance launch time
- Availability zone
- Kernel ID
- RAM disk ID
- Monitoring status
- Root device type (ebs or instance-store)
- Placement group the cluster instance is in

Example

```
euca-run-instances -k mykey -g mygroup emi-15A1386E
RESERVATION r-D8A4438A 790547641019 default
INSTANCE i-12623E16 emi-15A1386E 0.0.0.0 0.0.0.0 pending kp00
0 m1.small 2012-01-01T00:00:00.000Z zone00
```

euca-start-instances

Starts a stopped EBS-based instance.

Syntax

```
euca-start-instances instance_id
```

Options

Option	Description	Required
<i>instance_id</i>	Unique identifier for instance to start	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("INSTANCE")
- Instance ID

Example

```
euca-start-instances i-12623E16
INSTANCE    i-12623E16
```

euca-stop-instances

Stops a running EBS-based instance.

Syntax

```
euca-stop-instances instance_id [-f]
```

Options

Option	Description	Required
<i>instance_id</i>	Unique identifier for instance to stop	Yes
-f, --force	Forces the instance to stop	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier ("INSTANCE")
- Instance ID

Example

```
euca-stop-instances i-12623E16
INSTANCE    i-12623E16
```

euca-terminate-instances

Terminates the specified instances.

Syntax

```
euca-terminate-instances instance_id
```

Options

Option	Description	Required
<i>instance_id</i>	Unique identifier for instance to terminate	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("INSTANCE")
- Instance ID

Example

```
euca-terminate-instances i-12623E16
INSTANCE i-12623E16
```

euca-unbundle

Unbundles a previously uploaded bundle and extracts the image from it. You must have the X.509 certificate that was used to create the bundle.

Syntax

```
euca-unbundle -m manifest_path [-k private_key_path ]
               [-d destination_dir ] [-s source_dir ]
```

Options

Option	Description	Required
<code>-m, --manifest <i>manifest</i></code>	Path to the manifest file	Yes
<code>-k, --privatekey <i>private_key</i></code>	Path to private key used to encrypt bundle	Yes
<code>-d, --destination <i>destination_directory</i></code>	Directory to store the image to. Defaults to the current directory.	No
<code>-s, --source <i>source_directory</i></code>	Source directory for the bundled image parts. Defaults to manifest directory.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns status messages indicating the various stages of the unbundling process.

Example

```
euca-unbundle -m /tmp/myimage.img.manifest.xml
Part: myimage.img.part.00
Part: myimage.img.part.01
Part: myimage.img.part.02
Part: myimage.img.part.03
Decrypting image
Uncompressing image
```

euca-unbundle-stream

Recreate an image solely from its combined bundled parts without using a manifest.

Syntax

```
euca-unbundle-stream --enc-key hex --enc-iv hex
[-i filename] [-o filename]
  [--image-size bytes] [--sha1-digest hex]
  [--progress | --no-progress]
  [--region user@region] [--debug] [--debugger]
  [--version] [-h]
```

Options

Option	Description	Required
--enc-key <i>hex</i>	The symmetric key used to encrypt the bundle.	Yes
--enc-iv <i>hex</i>	The initialization vector used to encrypt the bundle	Yes
-i <i>filename</i>	File to read the bundle from. Defaults to <code>stdin</code> .	No
-o <i>filename</i>	File to write the bundle to. Defaults to <code>stdout</code> .	No
--image-size <i>bytes</i>	Verify the unbundled image is the specified size in bytes.	No
--sha1-digest <i>hex</i>	Verify the image's contents against a SHA1 digest from its manifest file.	No
--progress	Show a progress bar during command execution. This is the default when this command is run interactively.	No
--no-progress	Do not show a progress bar during command execution. This is the default when this command is run non-interactively.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.

Option	Description
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euca-unmonitor-instances

Disables monitoring for running instances.

Syntax

```
euca-unmonitor-instances instance_id [instance_id...]
```

Options

Option	Description	Required
<i>instance_id</i> [<i>instance_id...</i>]	Unique identifier for instance to stop monitoring	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

This command returns a table that contains the following information:

- The instance ID
- The monitoring state

Example

The following example disables monitoring for instances i-43a4412a and i-23a3397d.

```
euca-unmonitor-instances i-43a4412a i-23a3397d
i-43a4412a monitoring-disabling
i-23a3397d monitoring-disabling
```

euca-upload-bundle

Uploads a previously bundled image to the cloud.

Syntax

```
euca-upload-bundle -b bucket_name -m manifest_file
```

Options

Option	Description	Required
-b, --bucket <i>bucket_name</i>	Name of the bucket to upload to	Yes
-m, --manifest <i>manifest_file</i>	Path to the manifest file for bundled image	Yes
--acl	Canned access policy	No
--ec2cert <i>cert_path</i>	Path to the cloud's X509 public key certificate	No
-d, --directory <i>directory</i>	The directory containing the bundled image to upload. Defaults to the manifest directory.	No
--part	Uploads specified part and all subsequent parts	No
--skipmanifest	Do not upload the manifest	No
--location	The location of the destination S3 bucket Valid values: US EU us-west-1 ap-southeast-1 ap-northeast-1	

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.

Option	Description
<code>--security-token <i>token</i></code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns status messages that indicate the stages and status of the upload process.

Example

```
euca-upload-bundle -b mah-bukkit -m /tmp/myimage.img.manifest.xml
Checking bucket: mah-bukkit
Creating bucket: mah-bukkit
Uploading manifest file
Uploading part: myimage.img.part.00
Uploading part: myimage.img.part.01
Uploading part: myimage.img.part.02
Uploading part: myimage.img.part.03
Uploaded image as mah-bukkit/myimage.img.manifest.xml
```

euca-version

Displays version of Euca2ools.

Syntax

```
euca-version
```

Options

None

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region <i>user@region</i></code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url <i>url</i></code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id <i>key_id</i></code>	User's access key ID.
<code>-S, --secret-key <i>secret_key</i></code>	User's secret key.

Option	Description
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the version number of Euca2ools, along with its codename.

Example

```
euca-version
euca2ools 3.0.0 (Sparta)
```

IAM-Compatible Commands

Commands that begin with the `euare-` prefix are compatible with AWS Identity Management and Access Control (IAM).

euare-accountaliascreate

An account has two identifiers: a numeric ID and a human-readable alias. For a new account, the human-readable alias is the name given at the account's creation time. If you deleted your account alias, use this command to add a new one using your account's numeric ID.

Syntax

```
euare-accountaliascreate -a account_alias [--as-account account]
```

Options

Option	Description	Required
<code>-a, --account-alias <i>account_alias</i></code>	The new alias for the account.	Yes

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Examples

The following example adds an alias to your own account.

```
euare-accountaliascreate -a myacct
```

The following example adds an alias to another account as the cloud administrator.

```
euare-accountaliascreate -a myacct --as-account 612184482095
```

euare-accountaliasdelete

Deletes an alias for your account.

Syntax

```
euare-accountaliasdelete -a account_alias [--as-account account]
```

Options

Option	Description	Required
-a, --account-alias <i>account_alias</i>	The alias you want to delete.	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Examples

The following example deletes an alias for an account that you own.

```
euare-accountaliasdelete -a myacct
```

The following example deletes another account's alias as the cloud administrator.

```
euare-accountaliasdelete -a myacct --as-account myacct
```

This command also works with the numeric ID of the account in question for the as-account option, but not the -a option. For example:

```
euare-accountaliasdelete -a myacct --as-account 612184482095
```

euare-accountaliaslist

Lists the alias for your account.

Syntax

```
euare-accountaliaslist
```

Options

None

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns a list of aliases for the account ID making the request.

Example

```
euare-accountaliaslist
Alias: myacct
```

euare-accountcreate

Creates a new account. You must be a cloud administrator to use this command.

Syntax

```
euare-accountcreate [-k] [-w] [-d DOMAIN] [-l] [--show-empty-fields]
                    [-U URL] [--region USER@REGION] [-I KEY_ID]
                    [-S KEY] [--security-token TOKEN] [--debug]
                    [--debugger] [--version] [-h]
                    [ACCOUNT]
```

Options

Option	Description	Required
ACCOUNT	Also add an alias (name) to the new account (required on eucalyptus versions older than version 4.2)	No
-k, --create-access-key	Also create an access key for the new account's administrator and show it	No
-w, --write-config	Output access keys and region information in the form of a euca2ools.ini configuration file instead of by themselves (implies -k)	No
-d, --domain DOMAIN	DNS domain to use for region information in configuration file output (default: based on IAM URL)	No
-l, --set-default-user	Set this user as the default user for the region in the euca2ools.ini configuration file output. This option is only useful when used with the -w parameter.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns the account name and the generated account ID.

Example

The following example creates an account named 'bob' and emails the credentials.

```
euare-accountcreate bob -wld mycloud.example.com | mail -s "Your credentials"
bob@example.com
```

euare-accountdel

Deletes an account. You must be a cloud administrator to use this command.

Syntax

```
euare-accountdel -a account_name
```

Options

Option	Description	Required
-a, --account-name <i>account_name</i>	The name of the account to delete.	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-accountdel -a myacct
```

euare-accountdelpolicy

Deletes an account's policy. You must be a cloud administrator or an account administrator to use this command.

Syntax

```
euare-accountdelpolicy -a account_name -p policy_name
```

Options

Option	Description	Required
-a, --account-name <i>account_name</i>	Name of the account the policy is associated with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy document to delete	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-accountdelpolicy -a myacct -p mypolicy
```

euare-accountgetpolicy

Gets an account's policy.

Syntax

```
euare-accountgetpolicy -a account_name -p policy_name [--as-account account]
```

Options

Option	Description	Required
-a, --account-name <i>account_name</i>	Name of the account the policy is associated with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy to return	Yes
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns the account policy.

Example

```
euare-accountgetpolicy -a myacct -p mypolicy
<IAM policy>
```

euare-accountgetsummary

Returns number of groups and users in your account.

Syntax

```
euare-accountgetsummary
```

Options

None

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns a list of entity quotas and number of entities used.

Example

```
euare-accountgetsummary
Groups: 1
Users: 1
```

euare-accountlist

Lists accounts in the system

Syntax

```
euare-accountlist
```

Options

None

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.

Option	Description
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns a list of all account names and associated account IDs.

Example

```
euare-accountlist
eucalyptus      790547641019
myacct         612184482095
```

euare-accountlistpolicies

Lists all policies for an account.

Syntax

```
euare-accountlistpolicies -a account_name
```

Options

Option	Description	Required
<code>-a, --account-name account_name</code>	The name of the new account	Yes

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.

Option	Description
<code>--security-token=token</code>	Security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns a listing of all policies associated with the account.

Example

```
euare-accountlistpolicies -a myacct
mypolicy
```

euare-accountuploadpolicy

Uploads a policy to an account.

Syntax

```
euare-accountuploadpolicy -a account_name -p
policy_name [-o policy_content | -f policy_document]
```

Options

Option	Description	Required
<code>-a, --account-name</code> <i>account_name</i>	Name of the account the policy is associated with	Yes
<code>-p, --policy-name</code> <i>policy_name</i>	Name of the policy document to upload	Yes
<code>-o, --policy-content</code> <i>policy_content</i>	The policy document content. Include this content if you do not include the <code>policy-document</code> option.	Conditional
<code>-f, --policy-document</code> <i>policy_document</i>	The policy document file. Include this file if you do not include the <code>policy-content</code> option.	Conditional

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.

Option	Description
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Examples

The following example uploads a policy using the policy content in the command.

```
euare-accountuploadpolicy -a myacct -p mypolicy -o '<IAM policy>'
```

The following example uploads a policy using content in a policy file.

```
euare-accountuploadpolicy -a myacct -p mypolicy -f <file containing IAM policy>
```

euare-assumerole

Assume a role by using the Amazon Resource Name (ARN) to get temporary security credentials for that role. Then configure those credentials so subsequent actions work using the role's permissions. The ARN always prepends to the left of the command to complete the string.

Syntax

```
eval `euare-assumerole arn [--as-account account] [-d duration]
```

Options

euare-assumerole accepts common options similar to most other euare commands, but note the difference with the `#U/- -url` option in the table below.

Option	Description	Required
<code>arn:aws:iam::ARN</code>	ARN is the role you want to assume. <code>arn:aws:iam::ARN</code> should read either ARN or spell out each part of an ARN, as <code>arn:aws:iam</code> is part of an ARN. For example, when given <code>123456789012:role/S3Access</code> , it prepends the <code>arn:aws:iam::</code> to the entry as part of the ARN.	Yes
<code>-d duration</code>	The number of seconds for which the credentials it retrieves remain valid. Defaults to 900 or can be specified up to 3600.	No
<code>--session-name session</code>	Identifies the session and used to display your role's credentials. Can be randomly generated if not provided.	No

Option	Description	Required
-c	Generates C shell-compatible output. Default when the SHELL environment looks like C shell.	No
-s	Generates Bourne shell-compatible output. Defaults to this option if the SHELL environment does not look like C shell.	No
--policy-content-policy	The contents of an IAM policy that further limits what the assumed role can do. This option cannot grant additional permissions beyond what the role already allows.	No
--policy-document-file	A file of an IAM policy that further limits what the assumed role can do. This option cannot grant additional permissions beyond what the role already allows.	No
--external-id	A unique identifier that third parties can give to their customers to assume roles in their customers' accounts. For more information about external IDs, go to AWS External ID use case scenario .	No
--mfa-serial	The identification number of the Multi-Factor Authentication (MFA) device associated with the user who is assuming a role. If used, must be used in conjunction with -mfa-code.	No
--mfa-code	The code provided by the MFA device that allows access to the role that a user is assuming. If used, must be used in conjunction with --mfa-serial.	No
-U, --url	Points to the STS (tokens) service, not the IAM service. The matching environment variable for that is <code>TOKENS_URL</code> .	No

Output

Eucalyptus returns the policy.

euare-getldapsyncstatus

Retrieve the synchronization status for your LDAP and Eucalyptus policies database.

Syntax

```
euare-getldapsyncstatus
```

Options

None

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.

Option	Description
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Output type identifier ("SyncEnabled")
- Enabled status
- Output type identifier ("InSync")
- Synchronization status

Example

```
euare-getldapsyncstatus
SyncEnabled    false
InSync        false
```

euare-groupaddpolicy

Adds a new policy to a group.

Syntax

```
euare-groupaddpolicy -g group_name -p policy_name -e effect -a 'ec2:*'
-r resources [-o]
```

Options

Option	Description	Required
<code>-g, --group-name group_name</code>	Name of the group to associate the policy with	Yes
<code>-p, --policy-name policy_name</code>	Name of the policy document	Yes
<code>-e, --effect effect</code>	The value for the policy's <code>Effect</code> element. Valid values: <code>Allow</code> <code>Deny</code>	Yes
<code>-a, --action action</code>	The value for the policy's <code>Action</code> element. This value specifies both the service and action you want to allow or deny permission to. For example: <code>-a iam:ListAccessKeys</code> .	Yes
<code>-r, --resources resources</code>	Resource(s) the policy should apply to. At least one is required.	Yes

Option	Description	Required
-o	This option tells Eucalyptus to output the JSON policy document that IAM created for you.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Examples

The following policy allows all actions in EC2.

```
euare-groupaddpolicy -g mygroup -p mypolicy -e Allow -a 'ec2:*
```

The following policy allows all actions in EC2 and outputs the generated JSON policy.

```
euare-groupaddpolicy -g mygroup -p mypolicy -e Allow -a 'ec2:*' -o
{"Version": "2008-10-17", "Statement": [{"Effect": "Allow",
"Action": ["ec2:*"], "Resource": ["*"]}]}
```

euare-groupadduser

Adds a user to a group.

Syntax

```
euare-groupadduser -g group_name -u user_name
```

Options

Option	Description	Required
<code>-g, --group-name <i>group_name</i></code>	Name of the group the user will be added to	Yes
<code>-u, --user-name <i>user_name</i></code>	Name of the user to add to the group	Yes

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-groupadduser -g mygroup -u myuser
```

euare-groupcreate

Creates a group.

Syntax

```
euare-groupcreate -g group_name
```

Options

Option	Description	Required
<code>-g, --group-name <i>group_name</i></code>	Name of the group you want to create.	Yes
<code>-p, --path <i>path</i></code>	The path to the group. For more information about paths, go to Identifiers for IAM Entities . If you do not enter a value, the value defaults to a slash (/).	No
<code>-v, --verbose</code>	Causes the response to include the newly created group's Amazon resource name (ARN) and globally unique identifier (GUID).	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

If you send the `-v` option with this command, Eucalyptus returns the following:

- ARN
- GUID

Example

```
euare-groupcreate -g mygroup
euare-groupcreate -g mygroup -v
arn:aws:iam::eucalyptus:group/mygroup
UVKA2FRJJL12DHGBY7NIR
```

euare-groupdel

Deletes a group. If the group has users or policies, you must use the recursive option (`-r`) to delete all of them.

Syntax

```
euare-groupdel -g group_name
```

Options

Option	Description	Required
-g, --group-name <i>group_name</i>	Name of the group to delete	Yes
-r, --recursive	Deletes the group, removes all users from the group and deletes all policies associated with the group. .	No
-R, --recursive-euca	This Eucalyptus extension behaves exactly like the -r option but it performs operations server-side rather than in the client.	No
-p, --pretend	Returns a list of users and policies that would be deleted if the -r or -R option were actually sent in with the request.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-groupdel -g mygroup
```

euare-groupdelpolicy

Deletes a group policy.

Syntax

```
euare-groupdelpolicy -g group_name -p policy_name
```

Options

Option	Description	Required
-g, --group-name <i>group_name</i>	Name of the group the policy is associate with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy document to delete	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-groupdelpolicy -g mygroup -p mypolicy
```

euare-groupgetpolicy

Retrieves a group's policy to the console screen.

Syntax

```
euare-groupgetpolicy -g group_name -p policy_name
```

Options

Option	Description	Required
-g, --group-name <i>group_name</i>	Name of the group the policy is associate with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy document to get	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns the policy.

Example

```
euare-groupgetpolicy -g mygroup -p mypolicy
<IAM policy>
```

euare-grouplistbypath

Lists groups by path.

Syntax

```
euare-grouplistbypath [-p path]
```

Options

Option	Description	Required
<code>-p, --path-prefix <i>path</i></code>	The path prefix for filtering the results. For example, <code>/group_a/team_b/</code> returns all groups with a path that starts with <code>/group_a/team_b/</code> . If this parameter is empty, it defaults to a slash (<code>/</code>), listing all groups. Default: <code>/</code>	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the Amazon Resource Names (ARNs) that have the specified path prefix.

Example

The following example lists all groups.

```
euare-grouplistbypath
groups
  arn:aws:iam::eucalyptus:group/group01
  arn:aws:iam::eucalyptus:group/mygroup
```

euare-grouplistpolicies

Returns a listing of a group's policies.

Syntax

```
euare-grouplistpolicies -g group_name [-p policy_name]
```

```
euca2ools iam listpolicies -g mygroup --policy-name mypolicy
```

Options

Option	Description	Required
<code>-g, --group-name <i>group_name</i></code>	Name of the group to list policies for	Yes
<code>-p, --policy-name <i>policy_name</i></code>	Name of the policy document to display	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the contents of the policy you requested, or the names of the policies attached to the specified group (and optionally the contents of each).

Example

```
euca2ools iam listpolicies -g mygroup --policy-name mypolicy
```

euca2ools iam listusers

Returns a listing of the users in a group.

Syntax

```
euca2ools iam listusers -g group_name
```

Options

Option	Description	Required
<code>-g, --group-name group_name</code>	Name of the group to list users for	Yes

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus lists the Amazon Resource Names (ARNs) for the specified group.

Example

```
euare-grouplistusers -g mygroup
arn:aws:iam::eucalyptus:group/mygroup
  users
  arn:aws:iam::eucalyptus:user/myuser
```

euare-groupmod

Changes the name or path for a group.

Syntax

```
euare-groupmod -g group_name [-n new_group_name]
                  [-p new_path]
```

Options

Option	Description	Required
<code>-g, --group-name <i>group_name</i></code>	Name of the group you want to modify. If you are changing the name of the group, enter the original name for this value.	Yes
<code>--new-group-name</code>	New name for the group. Only include this if you are changing the group's name.	No
<code>-p, --new-path</code>	New path for the group. Only include this if you are changing the group's path.	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

The following example changes a group's name.

```
euare-groupmod -g mygroup -n mygroup2
```

The following example changes a group's path.

```
euare-groupmod -g mygroup -p /mypath
```

The following example changes a group's name and path.

```
euare-groupmod -g mygroup -n mygroup2 -p /mypath
```

euare-instanceprofileaddrole

Adds a role to an instance profile

Syntax

```
euare-instanceprofileaddrole -r role_name -s instance_profile
[--as-account ACCOUNT] [-U URL]
```

Options

Option	Description	Required
-r, --role-name <i>role_name</i>	Name of the role to add.	Yes
-i, --instance-profile <i>instanceprofilename</i>	Name of the instance profile.	Yes

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euare-instanceprofilecreate

Creates a new instance profile.

Syntax

```
euare-instanceprofilecreate -s instance_profile_name [-p path] [[-r role ] |
[--create-role]] [-v]
[--as-account account] [-U URL]
```

Options

Option	Description	Required
-s, --instance-profile-name <i>instance_profile_name</i>	Name of the new instance profile.	Yes
-p, --path <i>path</i>	Path for the instance profile. Default: "/"	No
-r, --add-role <i>role_name</i>	Add the specified role to the new instance profile. Cannot be specified if --create-role is specified.	No
--create-role	Create a role with the same name and path and add it to the new instance profile. Cannot be specified if --add-role is specified.	No
-v, --verbose	Display the new instance profile's ARN and GUID.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euare-instanceprofiledel

Deletes an instance profile.

Syntax

```
euare-instanceprofiledel -s instance_profile [-r] [-p] [--as-account account]
```

Options

Option	Description	Required
-s, --instance-profile-name <i>instance_profile_name</i>	Name of the instance profile to delete.	Yes
-r, --recursive	Remove all IAM resources associated with the instance profile first.	No
-p, --pretend	List the resources that would be deleted instead of actually deleting them.	No
-v, --verbose	Display the new instance profile's ARN and GUID.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euare-instanceprofilegetattributes

Deletes an instance profile.

Syntax

```
euare-instanceprofilegetattributes -s instance_profile [-r] [--as-account account]
```

Options

Option	Description	Required
-s, --instance-profile-name <i>instance_profile_name</i>	Name of the instance profile.	Yes
-r	List the roles associated with the instance profile.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euare-instanceprofilelistbypath

Lists all instance profiles for the current account.

Syntax

```
euare-instanceprofilelistbypath [-p prefix] [--as-account account]
```

Options

Option	Description	Required
-p, --path-prefix <i>instance_profile_name</i>	Limit results to instance profiles that begin with the given path.	Yes
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

euare-instanceprofilelistforrole

Lists all instance profiles that use a specified role.

Syntax

```
euare-instanceprofilelistforrole [-r role] [--as-account account]
```

Options

Option	Description	Required
<code>-r, --role-name role</code>	Role to list membership for.	Yes
<code>--as-account account</code>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.

Option	Description
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

euare-instanceprofileremoverole

Remove a role from an instance profile.

Syntax

```
euare-instanceprofileremoverole -r role -s profile_name [--as-account account]
```

Options

Option	Description	Required
<code>-r, --role-name role</code>	Name of the role to remove.	Yes
<code>-i, --instance-profile-name profile_name</code>	Name of the instance profile to remove the role from.	Yes
<code>--as-account account</code>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.

Option	Description
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

euare-getcallerid

Shows information about the currently-active credentials.

Syntax

```
euare-getcallerid [-U URL] [--region USER@REGION] [-I KEY_ID] [-S KEY]
                  [--security-token TOKEN] [--debug] [--debugger] [--version] [-h]
```

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns information about the account, ARN, key ID, and user ID associated with the currently active credentials.

Example

```
# euare-getcallerid
account = 000187952530
arn = arn:aws:iam::000187952530:user/admin
key-id = AKIAA3GFIXINJITSTQ2J
user-id = AIDAAPSETREWQ30VTYVJP
```

To check information about a user's credentials after the user assumed a role:

```
# eval $(euare-assumerole arn:aws:iam::eucalyptus:role/eucalyptus/
AccountAdministrator --session-name my-session)
#
# euare-getcallerid
```

```
account = 000187952530
arn = arn:aws:sts::000187952530:assumed-role/my-session
key-id = AKIAAFHJHJJ00ZSPZRCP
user-id = AROAAJZOMI2TIIY3GAUGF:my-session
#
```

euare-groupremoveuser

Removes a user from a group.

Syntax

```
euare-groupremoveuser -g group_name -u user_name
```

Options

Option	Description	Required
-g, --group-name <i>group_name</i>	Name of the group to remove the user from	Yes
-u, --user-name <i>user_name</i>	Name of the user to remove from the group	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-groupremoveuser -g mygroup -u myuser
```

euare-groupuploadpolicy

Uploads a policy for a group.

Syntax

```
euare-groupuploadpolicy -g group_name -p policy_name
                        [-o policy_content | -f policy_document]
```

Options

Option	Description	Required
-g, --group-name <i>group_name</i>	Name of the group the policy will be added to	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy document to upload	Yes
-o, --policy-content <i>policy_content</i>	The policy document content.	Conditional
-f, --policy-document <i>policy_document</i>	The policy document file.	Conditional

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

The following example uploads a policy using the policy content in the command.

```
euare-groupuploadpolicy -g mygroup -p mypolicy -o '<IAM policy>'
```

The following example uploads a policy using content in a policy file.

```
euare-groupuploadpolicy -g mygroup -p mypolicy -f <file containing IAM policy>
```

euare-releaserole

Reverse the effects of euare-assumerole by deleting the environment variables that command sets.

Syntax

```
eval euare-releaserole
```

Options

Option	Description	Required
-c	Generates C shell-compatible output. Default when the SHELL environment looks like C shell.	No
-s	Generates Bourne shell-compatible output. Defaults to this option if the SHELL environment does not look like C shell.	No

Output

Eucalyptus deletes the environment variables associated with previously assumed role.

euare-roleaddpolicy

Adds a new policy for a role.

Syntax

```
euare-roleaddpolicy -r role_name -p policy_name -e {Allow,Deny} -a actions  
-c resources [-o] [--as-account account]
```

Options

Option	Description	Required
-r, --role-name <i>role_name</i>	Name of the role to associate the policy with	Yes
-p, --policy-name <i>policy_name</i>	Name of the new policy	Yes
-e, --effect <i>effect</i>	The value for the policy's Effect element. Valid values: Allow Deny	Yes
-a, --action <i>action</i>	The value for the policy's Action element. This value specifies both the service and action you want to allow or deny permission to. For example: -a iam:ListAccessKeys.	Yes

Option	Description	Required
<code>-c, --actions actions</code>	Actions that the policy should apply to. At least one is required.	Yes
<code>--as-account account</code>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the policy

Example

The following policy allows myuser all actions in EC2.

```
euare-roleaddpolicy -r myrole -p mypolicy -e Allow -a 'ec2:*' -r '*'
```

The following policy allows myuser all actions in EC2 and outputs the generated JSON policy.

```
euare-roleaddpolicy -r myrole -p mypolicy -e Allow -a 'ec2:*' -r '*' -o
{"Version":"2008-10-17","Statement":[{"Effect":"Allow",
"Action":["ec2:*"], "Resource":["*"]}]}
```

euare-rolecreate

Creates a role.

Syntax

```
euare-rolecreate rolename [-p path] (-f filename | -s servicename)
[-v] [--as-account account]
```

Options

Option	Description	Required
<i>rolename</i>	Name of the role with which to associate the policy. This option is exclusive and positional.	Yes
-p , --path <i>path</i>	The path to the user. For more information about paths, go to Identifiers for IAM Entities . If you do not enter a value, the value defaults to a slash (/).	No
-f <i>filename</i>	Name of the file containing the new role's trust policy. Must be specified if <i>servicename</i> is not present.	No
-s , --service <i>servicename</i>	Name of the service to allow access to the role. Must be specified if <i>filename</i> is not present. Example: <code>ec2.amazonaws.com</code>	No
-v , --verbose	Display the new role's ARN GUID and policy.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region = <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url = <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key = <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key = <i>secret_key</i>	Override configured secret key with this value.
--security-token = <i>token</i>	Security token.
-D , --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h , --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns no message unless you requested it using **-v**. In that case, Eucalyptus outputs new role and policy information.

Example

The following example creates a role, *myrole*, with Amazon services access to it.

```
euare-rolecreate myrole -s ec2.amazonaws.com
```

euare-roledel

Deletes a role.

Syntax

```
euare-roledel -r rolename [-c] [-p] [--as-account account]
```

Options

Option	Description	Required
<code>-r, --role-name <i>user_name</i></code>	Name of the role to delete	Yes
<code>-c, --recursive</code>	Remove all IAM resources associated with the role first.	No
<code>-p, --pretend</code>	List the resources that would be deleted if the <code>-c</code> or <code>--recursive</code> option were actually sent in with the request.	No
<code>--as-account <i>account</i></code>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-roledel -r myrole
```

euare-roledelpolicy

Removes a policy from a role.

Syntax

```
euare-roledelpolicy -r rolename -p policy_name [--as-account account]
```

Options

Option	Description	Required
-r, --role-name <i>user_name</i>	Name of the role that the policy is associated with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy to delete	Yes
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-roledelpolicy -r myrole -p mypolicy
```

euare-rolegetattributes

Returns Amazon resource name (ARN) and user ID for a role.

Syntax

```
euare-rolegetattributes -r rolename [--as-account account]
```

Options

Option	Description	Required
-r , --role-name <i>user_name</i>	Name of the user whose attributes you want to get. If you don't specify this parameter, it defaults to the user making the request.	No
--show-extra	Display additional user information.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url , --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id , --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key , --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D , --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h , --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

When you use the **-u** option to specify a user, Eucalyptus returns the Amazon Resource Name (ARN) and user ID for that user. When you don't specify a user, Eucalyptus returns the ARN and the AWS account ID of the user making the request.

Examples

The following example returns attributes for the user making the request.

```
euare-rolegetattributes
```

```
arn:aws:iam::myacct:user/admin
AJIEQXKKG5M7VKOU7LNLQ
```

The following example returns attributes for the user, myuser.

```
euare-rolegetattributes -u myuser
arn:aws:iam::myacct:user/myuser
QLNL7UOKV7M5GKKXQEIJA
```

euare-rolegetpolicy

Returns information about a role's policy.

Syntax

```
euare-rolegetpolicy -u user_name -p policy_name
[--pretty-print][--as-account account]
```

Options

Option	Description	Required
-r, --role-name <i>user_name</i>	Name of the role that the policy is associated with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy document to retrieve	Yes
--pretty-print	Reformat the policy output for legibility.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns the policy content.

Example

```
euare-rolegetpolicy -r myrole -p mypolicy
{"Version":"2008-10-17","Statement":[{"Effect":"Allow",
"Action":["ec2:*"], "Resource":["*"]}]}
```

euare-rolelistbypath

Lists all roles for the current account.

Syntax

```
euare-rolelistbypath [-p prefix] [--as-account account]
```

Options

Option	Description	Required
-p, --path-prefix <i>instance_profile_name</i>	Limit results to instance profiles that begin with the given path.	Yes
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euare-rolelistpolicies

List one specific policy or all policies attached to a role.

Syntax

```
euare-rolelistpolicies -r rolename [-v] [--pretty-print]
[--as-account account]
```

Options

Option	Description	Required
-r, --role-name <i>username</i>	The name of the role to list policies for	Yes
-p, --policy-name <i>polycyname</i>	Name of the policy document to display	No
-v, --verbose	Display the contents of the resulting policies (in addition to their names)	No
--pretty-print	When printing the contents of policies, reformat them for easier reading	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U url, --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S secret_key, --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns the contents of the specific policy you requested, or the names of the policies attached to the role and, optionally, the contents of each.

Example

```
euare-rolelistpolicies -r myrole
mypolicy
```

euare-roleupdateassumepolicy

Update a role's trust policy, the policy that grants an entity permission to assume a role.

Syntax

```
euare-roleupdateassumepolicy rolename (-f filename | -s service)
[-o][--as-account account]
```

Options

euare-roleupdateassumepolicy is a standard euare command. It accepts the same common options as the others.

Option	Description	Required
<i>rolename</i>	Name of the role with which to associate the policy. This option is exclusive and positional.	Yes
-f <i>filename</i>	Name of the file containing the new role's trust policy. Must be specified if <i>servicename</i> is not present.	No
-s, --service <i>servicename</i>	Name of the service to allow access to the role. Must be specified if <i>filename</i> is not present. Example: <code>ec2.amazonaws.com</code>	No
-o	Output the role's new trust policy.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Output

Eucalyptus returns the policy only if output was requested using **-o**. Otherwise, no errors indicate success.

euare-roleuploadpolicy

Uploads a policy for a user.

Syntax

```
euare-roleuploadpolicy -r rolename -p policyname (-o policycontent | -
f filename)
[--as-account account]
```

Options

Option	Description	Required
-r, --role-name <i>rolename</i>	Name of the role to attach the policy to	Yes
-p, --policy-name <i>policyname</i>	Name of the policy	Yes
-o, --policy-content <i>policy_content</i>	The policy content. Example: <pre>{ "Version": "2008-10-17", "Statement": [{ "Effect": "Allow", "Action": ["ec2:*"], "Resource": ["*"] }] }</pre>	No
-f, --policy-document <i>policy_document</i>	The policy document file.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U url, --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S secret_key, --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-roleuploadpolicy -r myrole -p mypolicy -f mypolicy.json
```

euare-useraddcert

Uploads a signing certificate.

Syntax

```
euare-useraddcert [-u user_name]
                  [-c certificate_text | -f certificate_file]
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user the signing certificate is for	Np
-c, --certificate-body <i>certificate_text</i>	The contents of the signing certificate.	Conditional
-f, --certificate-file <i>certificate_file</i> >	The file that contains the signing certificate	Conditional

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns a certificate ID that you will need to modify or delete the certificate in the future.

Example

The following example uploads a signing certificate as text for the user named myuser.

```
euare-useraddcert -u myuser -c '<PEM-encoded certificate>'
```

```
ER1AYGZEJ401BGRTYMYOH
```

The following example uploads a signing certificate as a .pem file for the user named myuser.

```
euare-useraddcert -u myuser -f <file containing PEM-encoded certificate>
ER1AYGZEJ401BGRTYMYOH
```

euare-useraddkey

Adds a new access key to the user sending the request, unless otherwise specified. Eucalyptus prints the secret access key to the console. We recommend that you write this to a file.

Syntax

```
euare-useraddkey [-w] [-d DOMAIN] [-l] [--as-account ACCOUNT] [-U URL]
  [--region USER@REGION] [-I KEY_ID] [-S KEY]
  [--security-token TOKEN] [--debug] [--debugger] [--version] [-h] USER
```

Positional Arguments

Argument	Description
USER	The user to whom the new key will belong (default: current user).

Options

Option	Description	Required
-w, --write-config	Output access keys and region information in the form of a euca2ools.ini(5) configuration file instead of by themselves.	No
-d, --domain DOMAIN	DNS domain to use for region information in configuration file output (default: based on IAM URL).	No
-l, --set-default-user	Set this user as the default user for the region in the euca2ools.ini configuration file output. This option is only useful when used with the -w parameter.	No
--as-account ACCOUNT	[Eucalyptus cloud admin only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.

Option	Description
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Access key ID
- Secret access key

Example

The following example generates new keys for the user who owns the requesting credentials.

```
euare-useraddkey
UDHYLIGYKLURDIBAIUEMJ
0VhKjLs4QVA8F3o9Xl2bFhheQJL0K5I30kByFGdm
```

The following example generates new keys for myuser.

```
euare-useraddkey myuser
JMEUIABIDRULKYGILYH DU
mdGFyBk03I5K0LJQehhFb2lX9o3F8AVQ4sLjKhV0
```

The following example adds keys for the user 'alice' and writes them to a file named alice.ini:

```
euare-useraddkey alice -w > ~/.euca/alice.ini
```

euare-useraddloginprofile

Creates a login profile. This gives the access to the Management Console.

Syntax

```
euare-useraddloginprofile -u user_name -p password
```

Options

Option	Description	Required
<code>-u, --user-name user_name</code>	Name of the user the login profile is for	Yes
<code>-p, --password password</code>	The new password for the user. If this parameter is not supplied, the command will prompt for a password.	No

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-useraddloginprofile -u myuser -p SeekritPa$$w0rd
```

euare-useraddpolicy

Adds a new policy for a user.

Syntax

```
euare-useraddpolicy -p polycynname -e {Allow,Deny} -u user -a action [-r RESOURCE]
```

Options

Option	Description	Required
<code>-u, --user-name user_name</code>	Name of the user to associate the policy with	Yes
<code>-p, --policy-name policy_name</code>	Name of the policy document	Yes
<code>-e, --effect effect</code>	The value for the policy's Effect element. Valid values: Allow Deny	Yes

Option	Description	Required
<code>-a, --action <i>action</i></code>	The value for the policy's Action element. This value specifies both the service and action you want to allow or deny permission to. For example: <code>-a iam:ListAccessKeys</code> .	Yes
<code>-o</code>	This option tells Eucalyptus to output the JSON policy document that <code>euare-useraddpolicy</code> created for you.	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the policy

Example

The following policy allows myuser all actions in EC2.

```
euare-useraddpolicy -u myuser -p mypolicy -e Allow -a 'ec2:*' -r '*'
```

The following policy allows myuser all actions in EC2 and outputs the generated JSON policy.

```
euare-useraddpolicy -u myuser -p mypolicy -e Allow -a 'ec2:*' -r '*' -o
{"Version": "2008-10-17", "Statement": [{"Effect": "Allow",
"Action": ["ec2:*"], "Resource": ["*"]}]}
```

euare-usercreate

Creates a user.

Syntax

```
euare-usercreate [-p PATH] [-g GROUP_NAME] [--verify] [-k] [-v | -w]
```

```
[-d DOMAIN] [-l] [--as-account ACCOUNT] [-U URL]
[--region USER@REGION] [-I KEY_ID] [-S KEY]
[--security-token TOKEN] [--debug] [--debugger]
[--version] [-h]
USER
```

Options

Option	Description	Required
USER	Name of the user to create	Yes
-g, --group-name <i>group_name</i>	Name of the group the user will belong to	No
-k, --create-accesskey	Use this option if you want to create an access key for the user	No
-p, --path <i>path</i>	The path to the user. For more information about paths, go to Identifiers for IAM Entities . If you do not enter a value, the value defaults to a slash (/).	No
-w, --write-config	Output access keys and region information in the form of a euca2ools.ini configuration file instead of by themselves (implies -k)	No
-d, --domain <i>DOMAIN</i>	DNS domain to use for region information in configuration file output (default: based on IAM URL)	No
-l, --set-default-user	Set this user as the default user for the region in the euca2ools.ini configuration file output. This option is only useful when used with the -w parameter.	No
--as-account <i>ACCOUNT</i>	[Eucalyptus cloud admin only] Run this command as the administrator of another account	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns no message unless you requested to create an access key for the user. In that case, Eucalyptus returns the access key ID and secret access key.

Examples

The following example creates a user, myuser, the group, mygroup.

```
euare-usercreate myuser -g mygroup
```

The following example creates a user, myuser and an access key for the user.

```
euare-usercreate myuser -k
FUZMHBQEXQKMJXTW00VWV
Q59p8G9ZG4ePQYsvo30MJdpaMuodIT52He1KVAt8
```

euare-usercreatecert

Creates a signing certificate for a user. This command is not part of the AWS IAM API.

Syntax

```
euare-usercreatecert -u user_name [--out filename] [--keyout filename]
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	User name	Yes
--out <i>filename</i>	Name of file to write the certificate to (default: <code>stdout</code>)	No
--keyout <i>filename</i>	Name of file to write the private to (default: <code>stdout</code>)	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.

Option	Description
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

- Certificate ID
- Certificate body
- Certificate's private key

Example

```
euca2ools usercreatecert
WULI2PENBESQMTYKGNARB
-----BEGIN CERTIFICATE-----
MIIDFjCCAF6gAwIBAgIHA42rnQh5wjANBgkqhkiG9w0BAQ0FADBBMQswCQYDVQQL
EwJVUzENMAsGA1UEChMEVXNlcjETMBEGA1UECxMKRXVjYX5cCHR1czE0MAwGA1UE
AxMFYWRtaW4wHhcNMTIwNjI1MTk1NDQyWhcNMTcwNjI1MTk1NDQyWjBBMQswCQYD
VQQLGwJVUzENMAsGA1UEChMEVXNlcjETMBEGA1UECxMKRXVjYX5cCHR1czE0MAwG
A1UEAxMFYWRtaW4wggEiMA0GCSqGSIb3DQEBAQUAA4IBDwAwggEKAoIBAQCxSG3k
pC80JSbFNoYnZUZAJqHwpYHSIdrvVjYBwOUQbuG+D5ABY7lGcrQ64TfR5IFZyByw
nkh3Ku6uKrRdRsPbMnawCkgqfh9rWImyYf5bxsQ23kSsjdFQ0eujw6lFLtBR0Xdk
zMeFQtQ2b0wJD2Ucu/YcNQy7/RCdGIMJVBjWX4tRGL19vwyjT+xybX2E0YdDUSFK
i1o8YAUI2J+ZzM6d4zZ6YrtDeWwpluavUUEGxrRGUFRK8Zb0sFr7IuWpDnQDWcc
9ESF8bExoAZoCI7XQmEFECTNYyJL/FSJOUAF36XVAWl6tyUhIqPCkRI60qNCvNL
WFDIT2AGD1kygOSLAGmBAAGjEzARMA8GA1UdEwEB/wQFMAMBAf8wDQYJKoZIhvcN
AQENBQADggEBAJtbToC9AaxkjMe7QM5qLEMuodBjsgSHi8rRZhKZu4QkkNENcwPj7
y1rtdeWiJAT0hJ6UyrgDnnXzedFnjkPmfap30gkzXJ0pgNtyo1L5u2PBBqLkNs1l
jSJ007+MGwULMed/mlXUWYHCUKtbywo7i0Ek5U0zJng1Mf1S4UAHKREqvAnIybDn
D+xqDQLJeKjC59zb90Xf7aZ7Tk2v5ilv5i0Ir04aQCYN8+i59SY5g6PCFpQqm7p4
8/wm6qZ5YB79F71qWG70SHSdRv6aYp1KI1rf0ZXWhArHcw++Msg0uYcIJgkFpiBD
JrbC5t00Et6PuH9SDy0EovabypaXrna8aQI=
-----END CERTIFICATE-----
-----BEGIN RSA PRIVATE KEY-----
MIIEogIBAAKQAQEASUht5KQvDiUmXtaGJ2VMwI6h8KWB0iHa71Y2AcD1EG7hvg+Q
AW05RnK00uE30eSBWcgcsJ5B9yruriq0XUbd2zJ2sApIKn4fa1iJsmH+W8bEnt5E
rI3RUDnro1upRS7QUdFw5MzHhULUNm9MCQ9lHLv2HDUMu/0QnRiDCVQY1l+LURi9
fb8Mo0/scm19hNGHQ1LBSotaPGAFcNifmcz0neM2emK7Q3lsKS7mr1FHhsa0RlBS
kZPGW9LBA+yLlqQ50A1gnPREhfGx6AGaAi010JhBRckzWGIy/xUiTlAH9+1lQFp
erc1lSIJDwpES0jqjQrzS1nwyE9gBg9ZMoDkiwIDAQABAoIBADR3DeajXDWgcwfc
KfmQthUqY0x53qCUWlmINvVv45poZjA8JM70d0LM+t+N9VoNe0ZcHXl7bGQ8dWrf
yP7tyVqeZZeVg2Pn7V50VlPPQlpgyYK/Zq12TuKiMYUnxEFwKEB+bh2YKNfcpjdZ
zr03taG6UoxoertLmlyTgfwJwjKF0V3Y54ATvb0GasNq88l8qCMfHCSVC//OnxMJ
2/Bcta0F0LIqWUjWysPA1hxPr2rI4F1fZrdLTFgIXg9DZrYMNQIj/cHQjU/yiB1z
VZBbABjnGgRtN+SQKhk9ecjwVv4tXrXP1u4tJDJMKQGjcs+83ZW18jevNRVfZzIu
kYFSDjECgYEA3iJ9tspG05GDyR0dBZyqtpRt647e9sn56+/3nU7RFuj6DpoJKSDT
Av3+UoQSifswuMSWA+CgG0GwKxngyeR4NhKspqFKDIJo6a9h5ouFbM3DswW1KlBm
swWgYI1cPNKSDcfmAF8DiJsYcTEKVOComdrazp3iEvsWYCUQE94kVEKCGYEAzE90
es1aP+TMjMw00B9EFTredMZ3yBtDHxt7Dts3Z5vrJQaK6r9bMYFpp32f3UHFiaWA
SD2kjiYEkYaTnqC0EyR3/HoLmkHE/rjXDQI9ho/IXA3T0LuZbLkKMMULVlDKqGkJ6
Slcp1RpkhOAs/Tzz7/bR0mv0YNZ2SeyVkvzuvSjMCgYAUxGh8c+8Ak7g7izX5a989
R/FBDop+W10r3u0BE2gULf+yeHec+9r0bxBbTHFKFwDuLylyGd0QHdpUxIvjlYk3
r+IUz0jVf4pB63a1VT09nhxQDCY0dfqkNnJodFhh4rQf6C6auTnVkvkg9q6sgEmC
1uh/4vfcGmGA2cto2h4e8QKBgHAKBmMtZ5dwPefcn6qrIqfNv54kFB2tLZLKfCI6
```

```
ftiXfUyxmM6An163jBvoXRl1bwE7u+xhuXJL2IGZp9vmzCAKDhRKTmvZXsWHAARQ
VggUwyAHK7zoYA1OrvUA3KTHX9bEq9FGmU8eiQ8A7Er2+QKXxEcYkwcb408dI3o
Bg1XAoGAFJVjzeIzb5fuCG9wNU1YpEshOGlqgaQmAoFq36T1tP2EK2Zxb9rTI9FS
csCzeUKCU9D0gQKUmwGHsrDxJFpn+BglvX5su/77diITdh8/lwQFn0MQvligDBcv
4Ir5SjQApIMiy/R+rf5CWtR91rFn6hfxLwQ00lXzwyH+9UYFwsQ=
-----END RSA PRIVATE KEY-----
```

euare-userdel

Deletes a user.

Syntax

```
euare-userdel -u user_name [-r]
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user to delete	Yes
-r, --recursive	Deletes the user from associated groups and deletes the user's credentials and policies along with the user.	No
-R, --recursive-euca	This Eucalyptus extension behaves exactly like the -r option but it performs operations server-side rather than in the client.	No
-p, --pretend	Returns a list of users and policies that would be deleted if the -r or -R option were actually sent in with the request.	No

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-userdel -u myuser
```

euare-userdelcert

Deletes a signing certificate.

Syntax

```
euare-userdelcert -u user_name [-c certificate_id]
```

Options

Option	Description	Required
-u , --user-name <i>user_name</i>	Name of the user that the signing certificate belongs to	Yes
-c , --certificate-id <i>certificate_id</i>	ID of the signing certificate to delete	Yes

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url , --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id , --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key , --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D , --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h , --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-userdelcert -u myuser -c PXNPRNAHHMPLECYXCOMLE
```

euare-userdelkey

Deletes an access key. If the user is a member of any group or has user policies, signing certificates, access keys, and a login profile, you must use the recursive option.

Syntax

```
euare-userdelkey [-u user_name] -k user_key_id [-r]
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user that the access keys belongs to	No
-k, --user-key-id	The access key ID for the access key ID and secret access key you want to delete.	Yes
-r, --recursive	Deletes the user from associated groups and deletes the user's credentials and policies along with the user.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-userdelkey -u myuser -k UDHYLIGYKLURDIBAIUEMJ
```

euare-userdelloginprofile

Deletes a login profile.

Syntax

```
euare-userdelloginprofile -u user_name
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user whose profile you want to delete	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-userdelloginprofile -u myuser
```

euare-userdelpolicy

Deletes a user policy.

Syntax

```
euare-userdelpolicy -u user_name -p policy_name
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user that the policy is associated with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy document to delete	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-userdelpolicy -u myuser -p mypolicy
```

euare-usergetattributes

Returns Amazon resource name (ARN) and user ID for a user.

Syntax

```
euare-usergetattributes -u user_name [--show-extra] [--as-account account]
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user whose attributes you want to get. If you don't specify this parameter, it defaults to the user making the request.	No
--show-extra	Display additional user information.	No
--as-account <i>account</i>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

When you use the -u option to specify a user, Eucalyptus returns the Amazon Resource Name (ARN) and user ID for that user. When you don't specify a user, Eucalyptus returns the ARN and the AWS account ID of the user making the request.

Examples

The following example returns attributes for the user making the request.

```
euare-usergetattributes
arn:aws:iam::myacct:user/admin
AJIEQXKKG5M7VKOU7LNLQ
```

The following example returns attributes for the user, myuser.

```
euare-usergetattributes -u myuser
arn:aws:iam::myacct:user/myuser
```

```
QLNL7U0KV7M5GKKXQEIJA
```

euare-usergetinfo

Returns user information. This is not part of the AWS IAM API.

Syntax

```
euare-usergetinfo -u user_name [-k info_key]  
[-i info_value]
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user whose information you want to get.	No
-k, --info-key <i>info_key</i>	Specifies the name of the user information to get Default: email	No
-i, --info-value <i>info_value</i>	Specifies the value of the user information to set. If this value is empty, the existing information is removed, and not set to anything else.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

- Output type identifier
- Email address

Example

```
euare-usergetinfo
email    eucalyptus@example.com
```

euare-usergetloginprofile

Returns user name for a user.

Syntax

```
euare-usergetloginprofile -u user_name
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user whose login profile you want to get.	Yes

Common Options

Option	Description
--region=region	Region to direct requests to.
-U url, --url=url	Override service URL with this value.
--as-account account	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I access_key_id, --access-key=access_key_id	Override configured access key ID with this value.
-S secret_key, --secret-key=secret_key	Override configured secret key with this value.
--security-token=token	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

If the specified user has a profile, Eucalyptus returns the user's username. If the user has no profile, Eucalyptus returns an error.

Example

The following example shows the response for a user who has a profile.

```
euare-usergetloginprofile -u myuser
myuser
```

The following example shows the response for a user who has no profile.

```
euare-usergetloginprofile -u myuser
Error(NoSuchEntity): Can not find login profile for myuser
```

euare-usergetpolicy

Returns information about a user's policy.

Syntax

```
euare-usergetpolicy -u user_name -p policy_name
```

Options

Option	Description	Required
-u, --user-name <i>user_name</i>	Name of the user that the policy is associated with	Yes
-p, --policy-name <i>policy_name</i>	Name of the policy document to get	Yes

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns the policy content.

Example

```
euare-usergetpolicy -u myuser -p mypolicy
{"Version":"2008-10-17","Statement":[{"Effect":"Allow",
```

```
"Action":["ec2:*"], "Resource":["*"]}]}}
```

euare-userlistbypath

List users by path.

Syntax

```
euare-userlistbypath [-p path]
```

Options

Option	Description	Required
-p, --path-prefix	The path prefix for filtering the results. For example, /division_abc/subdivision_xyz/ returns all groups with a path that starts with /division_abc/subdivision_xyz/. If this parameter is empty, it defaults to a slash (/), listing all users.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.
-S <i>secret_key</i> , --secret-key= <i>secret_key</i>	Override configured secret key with this value.
--security-token= <i>token</i>	Security token.
-D, --debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

Eucalyptus returns a list of the users and their paths.

Example

The following example lists all users.

```
euare-userlistbypath
arn:aws:iam::myacct:user/myuser
arn:aws:iam::myacct:user/path/myuser2
```

The following example lists all users in the `/path` path.

```
euare-userlistbypath -p /path
arn:aws:iam::myacct:user/path/myuser2
```

euare-userlistcerts

List signing certificates for a user.

Syntax

```
euare-userlistcerts -u user_name [-m marker]
                        [--max-items max_items]
```

Options

Option	Description	Required
<code>-u</code> , <code>--user-name</code> <i>user_name</i>	Name of the user to get certificates for. If you don't specify this parameter, it defaults to the user making the request.	No.

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url</code> , <code>--url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id</code> , <code>--access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key</code> , <code>--secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D</code> , <code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h</code> , <code>--help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns a list of active and inactive signing certificates for the user.

Example

```
euare-userlistcerts -u myuser
ER1AYGZEJ401BGRTYMYOH
Active
PXNPRNAHHMPLECYXCOMLE
```

`Inactive`

euare-userlistgroups

Lists groups that a user belongs to.

Syntax

```
euare-userlistgroups -u user_name
```

Options

Option	Description	Required
<code>-u, --user-name <i>user_name</i></code>	Name of the user you want the group information for	Yes

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the Amazon Resource Name (ARN) for each group the user belongs to.

Example

```
euare-userlistgroups -u myuser
arn:aws:iam::myacct:group/mygroup
```

euare-userlistkeys

Lists access keys for a user.

Syntax

```
euare-userlistkeys -u user_name
```

Options

Option	Description	Required
<code>-u, --user-name <i>user_name</i></code>	Name of the user you want the key information for. If you don't specify this parameter, it defaults to the user making the request.	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns active and inactive keys for the user.

Example

```
euare-userlistkeys -u myuser
BH5GNX2GRJLRB3IKFC2X8
Active
QLNL7UOKV7M5GKKXQEIJA
Inactive
```

euare-userlistpolicies

Lists a user's policies.

Syntax

```
euare-userlistpolicies -u user_name [-v] [--pretty-print]
[--as-account account]
```

Options

Option	Description	Required
<code>-u, --user-name <i>user_name</i></code>	The name of the user to list policies for	Yes
<code>-p, --policy-name <i>policy_name</i></code>	Name of the policy document to display	No
<code>-v, --verbose</code>	Display the contents of the resulting policies (in addition to their names)	No
<code>--pretty-print</code>	When printing the contents of policies, reformat them for easier reading	No
<code>--as-account <i>account</i></code>	[Eucalyptus cloud administrator only] Run this command as the administrator of another account.	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus returns the contents of the specific policy you requested, or the names of the policies attached to the user and, optionally, the contents of each.

Example

```
euare-userlistpolicies -u myuser
mypolicy
```

euare-usermod

Change the name and/or path of a user.

Syntax

```
euare-usermod [-n USER] [-p PATH] [--enabled {true,false}]

  [--pwd-expires YYYY-MM-DDThh:mm:ssZ]
  [--reg-status {REGISTERED,APPROVED,CONFIRMED}]
  [--as-account ACCOUNT] [-U URL] [--region USER@REGION] [-I KEY_ID]
  [-S KEY] [--security-token TOKEN] [--debug]
  [--debugger] [--version] [-h] USER
```

Positional Arguments

Argument	Description
USER	Name of the user to update.

Options

Option	Description	Required
-n, --new-user-name <i>USER</i>	New name for the user.	No
-p, --new-path <i>PATH</i>	New path for the user.	No
--new-user-name	New name for the user	No
--enabled	Enable (<i>true</i>) or disable (<i>false</i>) the user. This option is specific to Eucalyptus. Valid values: <i>true</i> <i>false</i>	No
--pwd-expires <i>YYYY-MM-DDThh:mm:ssZ</i>	New password expiration date, in ISO8601 format. This option is specific to Eucalyptus.	No
--reg-status	Status of the user's registration. This option is specific to Eucalyptus 4.1 and earlier, in which only <i>confirmed</i> users may access the system. Valid values: <i>registered</i> <i>approved</i> <i>confirmed</i>	No
--as-account <i>ACCOUNT</i>	Only Eucalyptus cloud administrators can run this command as the administrator of another account.	No

Common Options

Option	Description
--region= <i>region</i>	Region to direct requests to.
-U <i>url</i> , --url= <i>url</i>	Override service URL with this value.
--as-account <i>account</i>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
-I <i>access_key_id</i> , --access-key= <i>access_key_id</i>	Override configured access key ID with this value.

Option	Description
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-usermod -u myuser -p /path -n myuser2
```

euare-usermodcert

Updates a user's signing certificate.

Syntax

```
euare-usermodcert [-u user_name] -c certificate_id -s Active|Inactive
```

Options

Option	Description	Required
<code>-u, --user-name user_name</code>	The name of the user that the certificate belongs to	No
<code>-c, --certificate-id certificate_id</code>	The ID of the signing certificate you want to update.	Yes
<code>-s, --status Active Inactive</code>	The status you want to assign to the certificate. Enter <code>active</code> to use the certificate for API calls to Eucalyptus. Enter <code>inactive</code> to block the certificate for API calls to Eucalyptus. Valid values: <code>active</code> <code>inactive</code>	

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.

Option	Description
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-usermodcert -u myuser -c ER1AYGZEJ401BGRTYMYOH -s Inactive
```

euare-usermodkey

Modifies a user's access key status.

Syntax

```
euare-usermodkey [-u user_name] -k user_key_id -s Active|Inactive
```

Options

Option	Description	Required
<code>-u, --user-name user_name</code>	Name of the user that the access key belongs to	No
<code>-k, --user-key-id user_key_id</code>	The access key ID for the access key ID and secret access key you want to modify.	Yes
<code>-s, --status Active Inactive</code>	The status you want to assign to the certificate. Enter <code>active</code> to use the certificate for API calls to Eucalyptus. Enter <code>inactive</code> to block the certificate for API calls to Eucalyptus. Valid values: <code>active</code> <code>inactive</code>	Yes

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.

Option	Description
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-usermodkey -u myuser -k BH5GNX2GRJLRB3IKFC2X8 -s Inactive
```

euare-usermodloginprofile

Modifies a user's login profile.

Syntax

```
euare-usermodloginprofile -u user_name -p password
```

Options

Option	Description	Required
<code>-u, --user-name <i>user_name</i></code>	The user whose profile you want to change	Yes
<code>-p --password</code>	The new password for the user. If you don't specify this parameter, it defaults to the user making the request.	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.

Option	Description
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-usermodloginprofile -u myuser -p SeekritPa$$w0rd
```

euare-userupdateinfo

Changes a user's password.

Syntax

```
euare-userupdateinfo -u user_name -k info_key [-i info_value]
```

Options

Option	Description	Required
<code>-u, --user-name <i>user_name</i></code>	Name of the user	Yes
<code>-k, --info-key</code>	Specifies the name of the user information to update	Yes
<code>-i, --info-value</code>	Specifies the value of the user information to set. If this value is empty, the existing information is removed, and not set to anything else.	No

Common Options

Option	Description
<code>--region=<i>region</i></code>	Region to direct requests to.
<code>-U <i>url</i>, --url=<i>url</i></code>	Override service URL with this value.

Option	Description
<code>--as-account <i>account</i></code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I <i>access_key_id</i>, --access-key=<i>access_key_id</i></code>	Override configured access key ID with this value.
<code>-S <i>secret_key</i>, --secret-key=<i>secret_key</i></code>	Override configured secret key with this value.
<code>--security-token=<i>token</i></code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-userupdateinfo -u myuser -k foo -i bar
```

euare-useruploadpolicy

Uploads a policy for a user.

Syntax

```
euare-useruploadpolicy -u user_name -p policy_name  
[-o policy_content] [-f policy_document]
```

Options

Option	Description	Required
<code>-u, --user-name <i>user_name</i></code>	Name of the user	Yes
<code>-p, --policy-name <i>policy_name</i></code>	Name of the policy document to upload	Yes
<code>-o, --policy-content <i>policy_content</i></code>	The policy document content.	No
<code>-f, --policy-document <i>policy_document</i></code>	The policy document file.	No

Common Options

Option	Description
<code>--region=region</code>	Region to direct requests to.
<code>-U url, --url=url</code>	Override service URL with this value.
<code>--as-account account</code>	This Eucalyptus extension is for use by the system administrator to act as the account administrator of the specified account without changing to account administrator's role.
<code>-I access_key_id, --access-key=access_key_id</code>	Override configured access key ID with this value.
<code>-S secret_key, --secret-key=secret_key</code>	Override configured secret key with this value.
<code>--security-token=token</code>	Security token.
<code>-D, --debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

Output

Eucalyptus does not return any message.

Example

```
euare-useruploadpolicy -u myuser -p mypolicy -f mypolicy.json
```

Elastic Load Balancing Commands

Commands that begin with the `eulb-` prefix are compatible with Amazon Elastic Load Balancer.

eulb-configure-healthcheck

Configure health checking for instances registered with a load balancer.

Syntax

```
eulb-configure-healthcheck --healthy-threshold COUNT --interval SECONDS
                             --target PROTOCOL:PORT[/PATH] --timeout SECONDS
                             --unhealthy-threshold COUNT
                             ELB
```

Options

Option	Description	Required
<code>--healthy-threshold <i>COUNT</i></code>	Number of consecutive successful health checks required to mark instances as Healthy	Yes
<code>--interval <i>SECONDS</i></code>	Approximate interval between health checks	Yes
<code>--target <i>PROTOCOL:PORT[/PATH]</i></code>	Connection target for health checks	Yes
<code>--timeout <i>SECONDS</i></code>	Maximum health check duration	Yes
<code>--unhealthy-threshold <i>COUNT</i></code>	Number of consecutive successful health checks required to mark instances as Unhealthy	Yes
<code><i>ELB</i></code>	Name of the load balancer to modify	Yes

Common Options

Option	Description
<code>--region <i>USER@REGION</i></code>	Name of the region or user in config files to use to connect to the service
<code>-U <i>URL</i>, --url <i>URL</i></code>	Load balancing service endpoint URL
<code>-I <i>key_id</i>, --access-key-id <i>key_id</i></code>	User's access key ID
<code>-S <i>key</i>, --secret-key <i>key</i></code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns a confirmation of the health check.

Example

```
eulb-configure-healthcheck --healthy-threshold=30 --interval=60 -t HTTP:80/
index.html --timeout=120 --unhealthy-threshold 360 MyLoadBalancer
HEALTH_CHECK      HTTP:80/index.html      60      120      30      360
```

eulb-create-lb

Create a Load Balancer. After the load balancer is created, instances must be registered with it separately.

Syntax

```
eulb-create-lb --availability-zones ZONE1,ZONE2,...
               --listener "lb-port=PORT, protocol=PROTOCOL
                           instance-port=PORT, instance-protocol=PROTOCOL,
                           cert-id=ARN"
               ELB
```

Options

Option	Description	Required
--availability-zones <i>ZONE1,ZONE2,...</i>	Availability zones the load balancer should run in	Yes
--listener "lb-port= <i>PORT</i> , protocol={ <i>HTTP,HTTPS,SSL,TCP</i> }, instance-port= <i>PORT</i> , instance- protocol={ <i>HTTP,HTTPS,SSL,TCP</i> }, cert-id= <i>ARN</i> "	Port and protocol settings for the load balancer. This option may be used multiple times. <i>lb-port</i> and <i>protocol</i> specify the external port number and protocol, <i>instance-port</i> and <i>instance-protocol</i> specify the port and protocol to use for routing traffic to backend instances, and <i>cert-id</i> specifies the ARN of the server certificate to use for encrypted connections.	Yes (Minimum: <i>lb-port</i> , <i>protocol</i> , <i>instance- port</i>)
<i>ELB</i>	Name of the load balancer to create	Yes

Common Options

Option	Description
--region <i>USER@REGION</i>	Name of the region or user in config files to use to connect to the service
-U <i>URL</i> , --url <i>URL</i>	Load balancing service endpoint URL
-I <i>key_id</i> , --access-key-id <i>key_id</i>	User's access key ID
-S <i>key</i> , --secret-key <i>key</i>	User's AWS secret key
--show-empty-fields	Show empty fields using (<i>nil</i>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns the DNS name of the new load balancer.

Example

```
eulb-create-lb -z PARTI00 -l "lb-port=80, protocol=HTTP, instance-port=80,
instance-protocol=HTTP" MyLoadBalancer
DNS_NAME      MyLoadBalancer-972528928292.lb.localhost
```

eulb-create-lb-listeners

Add one or more listeners to a load balancer.

Syntax

```
eulb-create-lb-listeners --listener "lb-port=PORT, protocol=PROTOCOL,
instance-port=PORT, instance-
protocol=PROTOCOL,
ELB cert-id=ARN"
```

Options

Option	Description	Required
--listener "lb-port= <i>PORT</i> , protocol={ <i>HTTP, HTTPS, SSL, TCP</i> }, instance-port= <i>PORT</i> , instance-protocol={ <i>HTTP, HTTPS, SSL, TCP</i> }, cert-id= <i>ARN</i> "	Port and protocol settings for the load balancer. This option may be used multiple times. lb-port and protocol specify the external port number and protocol, instance-port and instance-protocol specify the port and protocol to use for routing traffic to backend instances, and cert-id specifies the ARN of the server certificate to use for encrypted connections.	Yes (Minimum: lb-port, protocol, instance-port)
<i>ELB</i>	Name of the load balancer to modify	Yes

Common Options

Option	Description
--region <i>USER@REGION</i>	Name of the region or user in config files to use to connect to the service
-U <i>URL</i> , --url <i>URL</i>	Load balancing service endpoint URL
-I <i>key_id</i> , --access-key-id <i>key_id</i>	User's access key ID
-S <i>key</i> , --secret-key <i>key</i>	User's AWS secret key
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns no output.

Example

```
eulb-create-lb-listeners -l "lb-port=22, protocol=TCP, instance-port=22,
instance-protocol=TCP" MyLoadBalancer
```

eulb-create-lb-policy

Add a new policy to a load balancer.

Syntax

```
eulb-create-lb-policy -n POLICY -t POLTYPE
                        [-a "name=NAME, value=VALUE"] [-A NAME=VALUE,...]
                        [--attributes-from-file FILE] [-U URL]
                        [--region USER@REGION] [-I KEY_ID] [-S KEY]
                        [--security-token TOKEN] [--debug] [--debugger]
                        [--version] [-h]
                        ELB
```

Options

Option	Description	Required
<i>ELB</i>	Name of the load balancer	Yes
<i>-n, --policy-name POLICY</i>	Name of the new policy	Yes
<i>-t, --policy-type POLTYPE</i>	Type of the new policy. For a list of policy types, use <code>eulb-describe-lb-policy-types</code> .	Yes
<i>-a, --attribute "name=NAME, value=VALUE"</i>	Name and value for each attribute associated with the new policy. Use this option multiple times to supply multiple attributes.	Conditional
<i>-A, --attribute "name=NAME, value=VALUE"</i>	Comma-delimited list of attribute names and values to associate with the new policy, each pair of which is separated by "=". This is a more concise alternative to the <i>-a/--attribute</i> option.	Conditional
<i>--attribute-from-file FILENAME</i>	Name of a file containing attribute names and values to associate with the new policy, one per line, each pair of which is separated by "=". Lines that are blank or begin with "#" are ignored.	Conditional

Common Options

Option	Description
<i>--region USER@REGION</i>	Name of the region or user in config files to use to connect to the service
<i>-U URL, --url URL</i>	Load balancing service endpoint URL
<i>-I key_id, --access-key-id key_id</i>	User's access key ID
<i>-S key, --secret-key key</i>	User's AWS secret key

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

eulb-create-tags

Add one or more tags to a load balancer.

Syntax

```
eulb-create-tags -t KEY=VALUE [-U URL] [--region USER@REGION]
                  [-I KEY_ID] [-S KEY] [--security-token TOKEN]
                  [--debug] [--debugger] [--version] [-h]
ELB
```

Options

Option	Description	Required
ELB	Name of the load balancer.	Yes
<code>-t KEY=VALUE</code>	Key and value of each tag to add.	Yes

Common Options

Option	Description
<code>--region USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id key_id</code>	User's access key ID
<code>-S key, --secret-key key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

eulb-delete-lb

Delete a load balancer. If the load balancer does not exist, this command still succeeds.

Syntax

```
eulb-delete-lb ELB
```

Options

Option	Description	Required
ELB	Name of the load balancer to delete	Yes

Common Options

Option	Description
<code>--region</code> <code>USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id</code> <code>key_id</code>	User's access key ID
<code>-S key, --secret-key</code> <code>key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns no output.

Example

```
eulb-delete-lb MyLoadBalancer
```

eulb-delete-lb-listeners

Remove one or more listeners from a load balancer. If a listener named with `--lb-ports` does not exist, this command still succeeds.

Syntax

```
eulb-delete-lb-listeners --lb-ports PORT1,PORT2,... ELB
```

Options

Option	Description	Required
<code>--lb-ports</code> <code>PORT1,PORT2,...</code>	Port numbers of the listeners to remove.	Yes
<code>ELB</code>	Name of the load balancer to delete	Yes

Common Options

Option	Description
<code>--region</code> <code>USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id</code> <code>key_id</code>	User's access key ID
<code>-S key, --secret-key</code> <code>key</code>	User's AWS secret key

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns no output.

Example

```
eulb-delete-lb-listeners --lb-ports 22 MyLoadBalancer
```

eulb-delete-tags

Deletes one or more tags from a load balancer.

Syntax

```
eulb-delete-tags -t KEY [-U URL] [--region USER@REGION]
                    [-I KEY_ID] [-S KEY] [--security-token TOKEN]
                    [--debug] [--debugger] [--version] [-h]
ELB
```

Options

Option	Description	Required
ELB	Name of the load balancer.	Yes
<code>-t, --tag KEY</code>	Key and value of tag to delete.	Yes

Common Options

Option	Description
<code>--region USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id key_id</code>	User's access key ID
<code>-S key, --secret-key key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

eulb-deregister-instances-from-lb

Remove one or more instances from a load balancer.

Syntax

```
eulb-deregister-instances-from-lb --instances INSTANCE1,INSTANCE2,... ELB
```

Options

Option	Description	Required
<code>--instances</code> <i>INSTANCE1, INSTANCE2, ...</i>	IDs of the instances to remove from the load balancer	Yes
<i>ELB</i>	Name of the load balancer to modify	Yes

Common Options

Option	Description
<code>--region</code> <i>USER@REGION</i>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id</code> <i>key_id</i>	User's access key ID
<code>-S key, --secret-key</code> <i>key</i>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns no output.

Example

```
eulb-deregister-instances-from-lb --instances i-50683D12 MyLoadBalancer
```

eulb-describe-instance-health

Show the state of instances registered with a load balancer

Syntax

```
eulb-describe-lbs [--show-long] [--instances INSTANCE1, INSTANCE2, ...] ELB
```

Options

Option	Description	Required
<code>--instances</code> <i>INSTANCE1, INSTANCE2, ...</i>	Limit results to specific instances	Yes
<i>ELB</i>	Name of the load balancer to describe instances for	Yes

Common Options

Option	Description
<code>--region</code> <i>USER@REGION</i>	Name of the region or user in config files to use to connect to the service

Option	Description
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id key_id</code>	User's access key ID
<code>-S key, --secret-key key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns a list of instances registered with the load balancer and their state

Example

```
eulb-describe-instance-health MyLoadBalancer
INSTANCE    i-59A041B8    InService
INSTANCE    i-DEB03DDF    InService
INSTANCE    i-40CC3EC1    InService
INSTANCE    i-71DD408F    InService
INSTANCE    i-B0733FFF    InService
```

eulb-describe-lb-attributes

Shows a load balancer's attributes.

Syntax

```
eulb-describe-lb-attributes [--show-empty-fields] [-U URL]
                             [--region USER@REGION] [-I KEY_ID] [-S KEY]
                             [--security-token TOKEN] [--debug]
                             [--debugger] [--version] [-h]
                             ELB
```

Options

Option	Description	Required
ELB	Name of the load balancer.	Yes

Common Options

Option	Description
<code>--region USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id key_id</code>	User's access key ID
<code>-S key, --secret-key key</code>	User's AWS secret key

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

eulb-describe-lbs

Show information about load balancers.

Syntax

```
eulb-describe-lbs [--show-long] [ELB]
```

Options

Option	Description	Required
<code>--show-long</code>	Show all information	No
<i>ELB</i>	Limit results to a specific load balancer	No

Common Options

Option	Description
<code>--region USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id key_id</code>	User's access key ID
<code>-S key, --secret-key key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns the name of the load balancer, its hostname, and the time of creation.

Example

```
eulb-describe-lbs
LOAD_BALANCER    MyLoadBalancer    MyLoadBalancer-972528928292.lb.localhost
                2013-05-15T23:31:32.806Z
```

```
eulb-describe-lbs --show-long
LOAD_BALANCER    MyLoadBalancer    MyLoadBalancer-972528928292.lb.localhost
{interval=30,target=TCP:80,timeout=5,healthy-threshold=3,unhealthy-
threshold=2}
PARTI00          i-1DF9440E          {protocol=HTTP,lb-port=80,instance-
protocol=HTTP,instance-port=80}
{owner-alias=972528928292,group-name=euca-internal-972528928292-
MyLoadBalancer}    2013-05-15T23:31:32.806Z
```

eulb-describe-lb-policies

Show information about load balancer policies.

Syntax

```
eulb-describe-lb-policies [-p POLICY1,POLICY2,...] [--show-long]
  [--show-empty-fields] [-U URL]
  [--region USER@REGION] [-I KEY_ID] [-S KEY]
  [--security-token TOKEN] [--debug]
  [--debugger] [--version] [-h]
  [ELB]
```

Options

Option	Description	Required
<code>--show-long</code>	Show all information.	No
<code>ELB</code>	Only show policies associated with a specified load balancer.	No
<code>-p POLICY1, POLICY2, ...,</code>	Limit results to one or more specified policies, passed as a comma-delimited list of policy names.	No

Common Options

Option	Description
<code>--region USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id key_id</code>	User's access key ID
<code>-S key, --secret-key key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns the name and type of the load balancer policy.

Example

```
eulb-describe-lb-policies
POLICY ELBSample-AppCookieStickinessPolicy AppCookieStickinessPolicyType
POLICY ELBSample-LBCookieStickinessPolicy LBCookieStickinessPolicyType
POLICY ELBSecurityPolicy-2014-10 SSLNegotiationPolicyType
POLICY ELBSecurityPolicy-2015-02 SSLNegotiationPolicyType
POLICY ELBSecurityPolicy-2011-08 SSLNegotiationPolicyType
POLICY ELBSecurityPolicy-2015-05 SSLNegotiationPolicyType
POLICY ELBSecurityPolicy-2014-01 SSLNegotiationPolicyType
```

eulb-describe-tags

Show the tags associated with one or more load balancers.

Syntax

```
eulb-describe-tags [--show-headers] [--show-empty-fields] [-U URL]
                  [--region USER@REGION] [-I KEY_ID] [-S KEY]
                  [--security-token TOKEN] [--debug] [--debugger]
                  [--version] [-h]
                  ELB [ELB ...]
```

Options

Option	Description	Required
<i>ELB</i> [<i>ELB ...</i>]	Names of one or more load balancers to show tags for.	Yes

Common Options

Option	Description
--region <i>USER@REGION</i>	Name of the region or user in config files to use to connect to the service
-U <i>URL</i> , --url <i>URL</i>	Load balancing service endpoint URL
-I <i>key_id</i> , --access-key-id <i>key_id</i>	User's access key ID
-S <i>key</i> , --secret-key <i>key</i>	User's AWS secret key
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

eulb-disable-zones-for-lb

Remove a load balancer from one or more availability zones.

Syntax

```
eulb-disable-zones-for-lb --availability-zones ZONE1,ZONE2,... ELB
```

Options

Option	Description	Required
--availability-zones <i>ZONE1,ZONE2,...</i>	Availability zones to remove the load balancer from	Yes
<i>ELB</i>	Name of the load balancer to modify	Yes

Common Options

Option	Description
<code>--region</code> <code>USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id</code> <code>key_id</code>	User's access key ID
<code>-S key, --secret-key</code> <code>key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns a list of availability zones.

Example

```
eulb-disable-zones-for-lb --availability-zones PARTI00 MyLoadBalancer
AVAILABILITY_ZONES PARTI01
```

eulb-enable-zones-for-lb

Add a load balancer to one or more availability zones.

Syntax

```
eulb-enable-zones-for-lb --availability-zones ZONE1,ZONE2,... ELB
```

Options

Option	Description	Required
<code>--availability-zones</code> <code>ZONE1,ZONE2,...</code>	Availability zones to add the load balancer to	Yes
<code>ELB</code>	Name of the load balancer to modify	Yes

Common Options

Option	Description
<code>--region</code> <code>USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id</code> <code>key_id</code>	User's access key ID

Option	Description
<code>-S key, --secret-key key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns a list of availability zones.

Example

```
eulb-enable-zones-for-lb --availability-zones PARTI00 MyLoadBalancer
AVAILABILITY_ZONES      PARTI01, PARTI00
```

eulb-modify-lb-attributes

Modify a load balancer's attributes.

Syntax

```
eulb-modify-lb-attributes [-U URL] [--region USER@REGION] [-I KEY_ID]
                        [-S KEY] [--security-token TOKEN] [--debug]
                        [--debugger] [--version] [-h]
                        ELB ATTR=VALUE [ATTR=VALUE ...]
```

Options

Option	Description	Required
ELB	Name of the load balancer.	Yes
ATTRIBUTE=VALUE [ATTRIBUTE=VALUE ...]	Name and value of each attribute to modify.	Yes

Common Options

Option	Description
<code>--region USER@REGION</code>	Name of the region or user in config files to use to connect to the service
<code>-U URL, --url URL</code>	Load balancing service endpoint URL
<code>-I key_id, --access-key-id key_id</code>	User's access key ID
<code>-S key, --secret-key key</code>	User's AWS secret key
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

eulb-register-instances-with-lb

Add one or more instances to a load balancer.

Syntax

```
eulb-register-instances-with-lb --instances INSTANCE1,INSTANCE2,... ELB
```

Options

Option	Description	Required
--instances <i>INSTANCE1,INSTANCE2,...</i>	IDs of the instances to add to the load balancer	Yes
<i>ELB</i>	Name of the load balancer to modify	Yes

Common Options

Option	Description
--region <i>USER@REGION</i>	Name of the region or user in config files to use to connect to the service
-U <i>URL</i> , --url <i>URL</i>	Load balancing service endpoint URL
-I <i>key_id</i> , --access-key-id <i>key_id</i>	User's access key ID
-S <i>key</i> , --secret-key <i>key</i>	User's AWS secret key
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Output

Eucalyptus returns the instance ID.

Example

```
eulb-register-instances-with-lb --instances i-1DF9440E MyLoadBalancer
INSTANCE      i-1DF9440E
```

Auto Scaling-Compatible Commands

Commands that begin with the `euscale-` prefix are compatible with Amazon Auto Scaling.

euscale-create-auto-scaling-group

Creates a new auto scaling group with the specified parameters.

Syntax

```
euscale-create-auto-scaling-group
AutoScalingGroupName
--launch-configuration value
--max-size value
--min-size value
[--availability-zones value[,value... ]]
[--default-cooldown value ]
[--desired-capacity value ]
[--grace-period value ]
[--health-check-type value ]
[--load-balancers value[,value... ] ]
[--tags value[,value,...]]
[--termination-policies value[,value,... ]]
```

Options

Option	Description	Required
<code>AutoScalingGroupName</code>	The name of the auto scaling group.	Yes
<code>--launch-configuration value</code>	The name of the launch configuration to associate with this auto scaling group.	Yes
<code>--max-size value</code>	The maximum size of the auto scaling group.	Yes
<code>--min-size value</code>	The minimum size of the auto scaling group.	Yes
<code>--availability-zones value1,value2,value3...</code>	A list of availability zones for the auto scaling group.	No
<code>--default-cooldown value</code>	The amount of time, in seconds, after a scaling activity completes before any further trigger-related scaling activities can start.	Yes
<code>--desired-capacity value</code>	The number of instances that should be running in the auto scaling group.	No
<code>--grace-period value</code>	Length of time in seconds after a new Amazon EC2 instance comes into service that Auto Scaling starts checking its health.	No
<code>--health-check-type value</code>	The type of health check: instance or load balancer. Valid values: <code>ec2</code> <code>elb</code>	No
<code>--load-balancers --value value1,value2,value3...</code>	A comma-delimited list of load balancers used by this auto scaling group.	No

Option	Description	Required
<code>--tags --value "key1=value1, key2=value2..."</code>	A comma-delimited list of tags for this auto scaling group.	No
<code>--termination-policies --value value1, value2, value3...</code>	A delimited list of termination policies for this auto scaling group.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

There is no output from this command if it is successful.

Examples

```
euscale-create-auto-scaling-group MyScalingGroup --launch-configuration
MyLaunchConfig --availability-zones PARTI00 --min-size 2 --max-size 5
```

euscale-create-launch-configuration

Creates a new auto launch configuration with the specified parameters. UNFINISHED DRAFT.

Syntax

```
euscale-create-launch-configuration
LaunchConfigurationName
--image-id value --instance-type value
[--block-device-mapping "key1=value1,
key2=value2..." ] [--monitoring-enabled/monitoring-disabled ]
[--kernel value ] [--key value ]
[--ramdisk value ] [--group value[,value... ] ]
[--user-data value ] [--user-data-file value ]
```

Options

Option	Description	Required
<code>LaunchConfigurationName</code>	The name of the launch configuration.	Yes
<code>--image-id value</code>	Unique ID of the Eucalyptus Machine Image (EMI) to use when launching new instances in the auto scaling group.	Yes
<code>--instance-type value</code>	The type of instance to launch.	Yes
<code>--block-device-mappings value1,value2,value3...</code>	A list of mappings that specify how block devices are mapped to instances launched in the auto scaling group.	No
<code>--monitoring-enabled / --monitoring-disabled</code>	Enables or disables euwatch metrics for instances launched in the auto scaling group.	No
<code>--kernel value</code>	The ID of the kernel associated with the EMI.	No
<code>--key value</code>	The name of a keypair that new instances in the scaling group should use.	No
<code>--ramdisk value</code>	The identifier of the ram disk associated with the EMI.	No
<code>--group value</code>	The name of the security group.	No
<code>--user-data value</code>	User data to be passed to launched instances.	No
<code>--user-data-file value</code>	Name of local file containing user data to be passed to launched instances.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

There is no output from this command if it is successful.

Examples

The follow example creates a launch configuration that specifies that new instances launched from will be of type `m1.small` and from image ID `emi-00123456`.

```
euscale-create-launch-config MyLaunchConfig --image-id emi-00123456 --
instance-type m1.small
```

euscale-delete-auto-scaling-group

Deletes the specified auto scaling group. UNFINISHED DRAFT.

Syntax

```
euscale-delete-auto-scaling-group
AutoScalingGroupName
[--force-delete value]
```

Options

Option	Description	Required
<code>AutoScalingGroupName</code>	The name of the auto scaling group to delete.	Yes
<code>--force-delete</code>	Specifies that the auto scaling group will be deleted along with all instances associated with the group, without waiting for all instances to be terminated.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns no output.

Examples

The follow example will delete an auto scaling group and all associated instances.

```
euscale-delete-auto-scaling-group myscalinggroup --force-delete
```

There is no output from this command upon succesful completion.

euscale-delete-launch-configuration

Deletes the specified launch configuration if it is not in use by an auto scaling group.

Syntax

```
euscale-delete-launch-configuration  
LaunchConfigurationName
```

Options

Option	Description	Required
LaunchConfigurationName	The name of the launch configuration to delete. Note: You cannot delete a launch configuration that is in use by an auto scaling group.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns nothing.

Examples

The follow example will delete an launch configuration and all associated instances.

```
euscale-delete-launch-configuration mylaunchconfiggroup
```

euscale-delete-policy

Deletes the specified policy.

Syntax

```
euscale-delete-policy
PolicyName
-g, --auto-scaling-group value]
```

Options

Option	Description	Required
Policy	The name of the policy to delete.	Yes
-g, --auto-scaling-group value	The name of the auto scaling group associated with the policy.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region value	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url value	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id value	User's access key ID
-S, --secret-key value	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns no output.

Examples

The follow example will delete a policy named `MyScaleinPolicy` in the auto scaling group named `MyScalingGroup`.

```
euscale-delete-policy MyScaleinPolicy -g MyScalingGroup
```

euscale-describe-adjustment-types

Describes specified or all valid adjustment types for scaling policies.

Syntax

```
euscale-describe-adjustment-types  
[AdjustmentType [AdjustmentType...]]
```

Options

Option	Description	Required
<i>AdjustmentType, AdjustmentType...</i>	AdjustmentType, AdjustmentType... to describe.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns a table that contains a list of the available adjustment types.

Examples

```
euscale-describe-adjustment-types
```

The following shows sample output for this command.

```
ADJUSTMENT-TYPE ChangeInCapacity
ADJUSTMENT-TYPE ExactCapacity
ADJUSTMENT-TYPE PercentChangeInCapacity
```

euscale-describe-auto-scaling-instances

Returns information about the specified auto scaling instance(s). If no instances are specified, this command returns information about all auto scaling instances. UNFINISHED DRAFT.

Syntax

```
euscale-describe-auto-scaling-instances
[InstanceId [InstanceId...]]
```

Options

Option	Description	Required
<i>InstanceId, InstanceIds</i>	Id of instance(s) to describe.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns a table that contains the instance ID, the availability zone, the instance status, the instance health, and the name of the launch configuration used to launch the instance.

Examples

The follow example will return information about all auto scaling instances.

```
euscale-describe-auto-scaling-instances
```

The following shows sample output for this command.

```
INSTANCE i-1B853EC3 PARTI00 InService Healthy MyLaunchConfig
INSTANCE i-ABC53ED7 PARTI00 InService Healthy MyLaunchConfig
```

euscale-describe-auto-scaling-groups

Returns information about the specified auto scaling group(s). If no instances are specified, this command returns information about all auto scaling instances.

Syntax

```
euscale-describe-auto-scaling-groups
[AutoScalingGroupName [AutoScalingGroupName... ] ]
```

Options

Option	Description	Required
<i>AutoScalingGroupName</i>	A list of AutoScalingGroupNames, AutoScalingGroupNames...	No

Common Options

Option	Description
<i>--show-empty-fields</i>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<i>--region value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<i>-U, --url value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<i>-I, --access-key-id value</i>	User's access key ID
<i>-S, --secret-key value</i>	User's AWS secret Key to use.
<i>--debug</i>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<i>--debugger</i>	Enable interactive debugger on error.
<i>--version</i>	Display the version of this tool.
<i>-h, --help</i>	Display the manual page for the command.

Output

This command returns a table that contains the auto scaling group name, the associated launch configuration, the availability zone, the minimum, maximum, and desired number of instances, and the security group. Each auto scaling group entry is followed by a listing of all of the instances in the auto scaling group. This list includes the instance ID, the instance's availability zone, status, health status, and launch configuration.

Examples

The follow example will return information about the auto scaling group named *myscalinggroup*.

```
euscale-describe-auto-scaling-groups myscalinggroup
```

The following shows sample output for this command.

```
AUTO-SCALING-GROUP MyScalingGroup MyLaunchConfig PARTI00 2 5 2 Default
INSTANCE i-1B853EC3 PARTI00 InService Healthy MyLaunchConfig
INSTANCE i-ABC53ED7 PARTI00 InService Healthy MyLaunchConfig
```

euscale-describe-launch-configs

Returns information about the specified launch configuration(s). If no launch configurations are specified, this command returns information about all launch configurations.

Syntax

```
euscale-describe-launch-configs
[LaunchConfigName [LaunchConfigName...]]
```

Options

Option	Description	Required
<i>LaunchConfigName, LaunchConfigName...</i>	A list of names of launch configurations to describe.	No

Common Options

Option	Description
<i>--show-empty-fields</i>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<i>--region value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<i>-U, --url value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<i>-I, --access-key-id value</i>	User's access key ID
<i>-S, --secret-key value</i>	User's AWS secret Key to use.
<i>--debug</i>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<i>--debugger</i>	Enable interactive debugger on error.
<i>--version</i>	Display the version of this tool.
<i>-h, --help</i>	Display the manual page for the command.

Output

See example below.

Examples

The follow example will return information about the launch configurations named *mylaunchconfig*.

```
euscale-describe-launch-configs MyLaunchConfig
```

The following shows sample output for this command.

```
LAUNCH-CONFIG MyLaunchConfig emi-69683886 m1.small
```

euscale-describe-metric-collection-types

Returns a list of all metric collection and metric granularity types.

Syntax

```
euscale-describe-metric-collection-types
```

Options

This command has no specific options.

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns a list of the available metric collection and granularity types.

Examples

```
euscale-describe-metric-collection-types
```

This command returns output similar to the following.

```
METRIC-COLLECTION-TYPE GroupDesiredCapacity
METRIC-COLLECTION-TYPE GroupInServiceInstances
METRIC-COLLECTION-TYPE GroupMaxSize
METRIC-COLLECTION-TYPE GroupMinSize
METRIC-COLLECTION-TYPE GroupPendingInstances
METRIC-COLLECTION-TYPE GroupTerminatingInstances
METRIC-COLLECTION-TYPE GroupTotalInstances
METRIC-GRANULARITY-TYPE 1Minute
```

euscale-describe-policies

Describes the specified (or all) policies.

Syntax

```
euscale-describe-policies
[PolicyName [PolicyName... ] ]
[-g, --auto-scaling-group value ]
```

Options

Option	Description	Required
<i>PolicyName, PolicyName...</i>	A list of one or more policies to describe.	No
-g, --auto-scaling-group value	Show only policies for the named auto scaling group.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns a table that contains the name of the auto scaling group associated with the policy, the name of the policy, the change value, the type of change, and the ARN of the scaling policy.

Examples

```
euscale-describe-policies
```

The following shows sample output for this command.

```
SCALING-POLICY MyScalingGroup MyScaleInPolicy -2 ChangeInCapacity
```

```
arn:aws:autoscaling::706221218191:scalingPolicy:90356ab3-e795-4741-b058-
a3499c8a6ee6
:autoScalingGroupName/MyScalingGroup:policyName/MyScaleinPolicy
SCALING-POLICY MyScalingGroup MyScaleoutPolicy 30 PercentChangeInCapacity
arn:aws:autoscaling::706221218191:scalingPolicy:5d02981b-
f440-4c8f-98f2-8a620dc2b787
:autoScalingGroupName/MyScalingGroup:policyName/MyScaleoutPolicy
```

euscale-describe-scaling-activities

Describes scaling activities for an auto scaling group.

Syntax

```
euscale-describe-scaling-activities
[ActivityId [ActivityId ...]]
[--auto-scaling-group value]
```

Options

Option	Description	Required
ActivityId [ActivityId ...]	A list of one or more activity IDs to use as a filter. If this parameter is not specified, all activity is returned.	No
-g, --auto-scaling-group value	Filter by the specified auto scaling group.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region value	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url value	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id value	User's access key ID
-S, --secret-key value	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns a table that contains the activity ID, the timestamp of the activity, the name of the scaling group, and a succeed or fail message.

Examples

euscale-describe-scaling-activities

The following shows sample output for this command.

```
ACTIVITY cc9f60de-64cf-4055-805c-54cf9305d91d 2013-05-03T07:59:03.257
MyScalingGroup Successful
ACTIVITY 194ea242-f7ea-4629-9f1e-a7ba46d435f3 2013-05-03T07:58:59.831
MyScalingGroup Successful
ACTIVITY 8ff9f6b7-1ce5-416a-aeeb-5ecaccb249c6 2013-05-02T06:33:33.181
MyScalingGroup Successful
ACTIVITY 459d2f55-f7d6-4062-9956-ad14ea6e7e7b 2013-05-02T06:33:23.452
MyScalingGroup Failed Failed to send message RunInstancesType to
service EucalyptusRequestQueue because: Batch entry 0 insert into
metadata_network_indices (creation_timestamp, last_update_timestamp,
metadata_perm_uuid, version, metadata_display_name, metadata_last_state, meta
ACTIVITY 02954224-6cfb-48b1-90d6-7ba3a63dd221 2013-05-02T06:33:23.381
MyScalingGroup Successful
```

euscale-describe-termination-policy-types

Returns a list of all termination policy types.

Syntax

euscale-describe-termination-policy-types

Options

This command has no specific options.

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns a table that lists the available termination policy types.

Examples

```
euscale-describe-termination-policy-types
```

This command returns output similar to the following.

```
TERMINATION-POLICY-TYPE OldestInstance
TERMINATION-POLICY-TYPE OldestLaunchConfiguration
TERMINATION-POLICY-TYPE NewestInstance
TERMINATION-POLICY-TYPE ClosestToNextInstanceHour
TERMINATION-POLICY-TYPE Default
```

euscale-disable-metrics-collection

Disables collection of auto scaling group metrics.

Syntax

```
euscale-disable-metrics-collection
AutoScalingGroupName --granularity value
[--metrics value [,value...]] ]
```

Options

Option	Description	Required
AutoScalingGroupName	The name of the auto scaling group.	Yes
-m, --metrics --value value1,value2,value3...	A delimited list of metrics to stop collecting. If this parameter is not specified, collection for all metrics will be disabled.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region value	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url value	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id value	User's access key ID
-S, --secret-key value	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.

Option	Description
-h, --help	Display the manual page for the command.

Output

This command returns no output.

Examples

```
euscale-disable-metrics-collection
```

euscale-enable-metrics-collection

Enables collection of auto scaling group metrics.

Syntax

```
euscale-enable-metrics-collection
AutoScalingGroupName --granularity value
[--metrics value [,value...]]
```

Options

Option	Description	Required
AutoScalingGroupName	The name of the auto scaling group.	Yes
-g, --granularity <i>value</i>	Specifies the unit of granularity to collect. Use <code>euscale-describe-metric-collection-types</code> to retrieve a list of valid values.	Yes
-m, --metrics <i>value</i> [, <i>value1</i> , <i>value2</i> , <i>value3</i>]	A delimited list of metrics to collect. If this parameter is not specified, all metrics are collected.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.

Option	Description
- -version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns no output.

Examples

```
euscale-enable-metrics-collection
```

euscale-execute-policy

Executes the specified scaling policy.

Syntax

```
euscale-execute-policy
PolicyID
-g, --auto-scaling-group-name value
[-h, --honor-cooldown / -H, --no-honor-cooldown ]
```

Options

Option	Description	Required
PolicyID	The ID of the policy to execute.	Yes
-g, --auto-scaling-group-name	The name or ARN of the auto scaling group.	Yes
-h, --honor-cooldown	Reject this request if the specified group is in cooldown.	No
-H, --no-honor-cooldown	Override the specified group's cooldown period. This is the default behavior.	No

Common Options

Option	Description
- -show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
- -region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.

Option	Description
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

Output

This command returns no output.

Examples

The follow example executes a scaling policy named `MyScaleinPolicy` in the scaling group `MyScalingGroup`.

```
euscale-execute-policy MyScaleinPolicy -g MyScalingGroup -H
```

This command has no output.

euscale-put-scaling-policy

Creates or updates a scaling policy.

Syntax

```
euscale-put-scaling-policy
PolicyName
-g, --auto-scaling-group value
[--adjustment value]
[-t, --adjustment-type value]
[--cooldown value]
[-s, --min-adjustment-step value]
```

Options

Option	Description	Required
PolicyName	The name of the policy.	Yes
-g, --auto-scaling-group value	The name of the auto scaling group associated with the policy.	Yes
-a, --adjustment value	The amount to scale the capacity of the group. Use a negative number to decrease capacity.	Yes
-t, --type value	Indicates the type of change for the --adjustment parameter. Valid values are: ChangeInCapacity A fixed-number increment of the old value ExactCapacity An absolute value PercentChangeInCapacity A percentage of the current capacity	Yes

Option	Description	Required
<code>--cooldown value</code>	The waiting period, in seconds, before auto scaling activities will resume.	Yes
<code>-s, --min-adjustment-step value</code>	The minimum adjustment value for <code>PercentageChangeInCapacity</code> -type adjustments.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns no output.

Examples

The follow example will delete a policy named `MyScaleinPolicy` in the auto scaling group named `MyScalingGroup`.

```
euscale-put-scaling-policy MyScaleinPolicy -g MyScalingGroup -a -1 -t
ChangeInCapacity
```

euscale-resume-processes

Resumes all scaling processes for the specified auto scaling group.

Syntax

```
euscale-resume-processes AutoScalingGroupName
```

Options

Option	Description	Required
<code>AutoScalingGroupName</code>	The name of the auto scaling group.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns nothing.

Examples

The follow example will return information about all auto scaling instances.

```
euscale-resume-processes MyScalingGroup
```

euscale-set-desired-capacity

Sets the desired capacity of the specified auto scaling group (within the range of the group's minimum and maximum size).

Syntax

```
euscale-set-desired-capacity
AutoScalingGroupName
--desired-capacity value
[--honor-cooldown/--no-honor-cooldown ]
```

Options

Option	Description	Required
<code>AutoScalingGroupName</code>	The name of the auto scaling group.	Yes

Option	Description	Required
-c, --desired-capacity	The new desired capacity for the auto scaling group.	Yes
-h, --honor-cooldown	Reject this request if the auto scaling group is in cooldown.	No
-H, --no-honor-cooldown	Override the cooldown period. This is the default.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euscale-set-instance-health

Sets the health of the instance.

Syntax

```
euscale-set-instance-health
InstanceID
--status value
[--respect-grace-period/--no-respect-grace-period ]
```

Options

Option	Description	Required
InstanceID	The ID of the instance.	Yes
-s, --status	The new status for the auto scaling group.	Yes
--respect-grace-period	Respect the associated auto scaling group's grace period.	No

Option	Description	Required
<code>--no-respect-grace-period</code>	Ignore the associated auto scaling group's grace period.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns no output.

Examples

```
euscale-set-instance-health i-00123456 --status InService --no-respect-grace-period
```

euscale-suspend-processes

Suspends all scaling processes for the specified auto scaling group.

Syntax

```
euscale-suspend-processes AutoScalingGroupName
```

Options

Option	Description	Required
<code>AutoScalingGroupName</code>	The name of the auto scaling group.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns nothing.

Examples

```
euscale-suspend-proceses MyScalingGroup
```

euscale-terminate-instance-in-auto-scaling-group

Manually terminate an instance in an auto scaling group.

Syntax

```
euscale-terminate-instance-in-auto-scaling-group (-d | -D)
[--show-long]
[--show-empty-fields]
[-U URL]
[--region USER@REGION]
[-I KEY_ID] [-S KEY]
[--security-token TOKEN]
[--debug] [--debugger]
[--version] [-h]
INSTANCE
```

Options

Option	Description	Required
InstanceID	The identifier of the instance to terminate.	Yes
<code>-d, --decrement-desired-capacity</code>	Also reduce the desired capacity of the associated auto scaling group by one.	No

Option	Description	Required
-D, --no-decrement-desired-capacity	Do not reduce the desired capacity of the associated auto scaling group. Auto scaling can launch a new instance to replace the instance terminated with this command.	No
--show-long	Show extra information about the instance being terminated.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

See the example below for output.

Examples

The follow example terminates an instance without decrementing the auto scaling group's capacity, showing extra information about the terminated instance.

```
euscale-terminate-instance-in-auto-scaling-group i-ABC53ED7 -D --show-long
```

The following shows sample output for this command.

```
INSTANCE 194ea242-f7ea-4629-9f1e-a7ba46d435f3 InProgress
At 2013-05-03T07:58:59Z instance was taken out of service in response to a
user
request.. 50 Terminating EC2 instance: i-ABC53ED7
2013-05-03T07:58:59.662Z
```

euscale-update-auto-scaling-group

Updates a new auto scaling group with the specified parameters. UNFINISHED DRAFT.

Syntax

```
euscale-update-auto-scaling-group
```

```

AutoScalingGroupName
--launch-configuration value
--max-size value
--min-size value
[--availability-zones value[,value... ]]
[--default-cooldown value ]
[--desired-capacity value ]
[--grace-period value ]
[--health-check-type value ]
[--tags value[,value,...]]
[--termination-policies value[,value,... ]]

```

Options

Option	Description	Required
AutoScalingGroupName	The name of the auto scaling group.	Yes
--launch-configuration <i>value</i>	The name of the launch configuration to associate with this auto scaling group.	Yes
--max-size <i>value</i>	The maximum size of the auto scaling group.	Yes
--min-size <i>value</i>	The minimum size of the auto scaling group.	Yes
--availability-zones <i>value1,value2,value3...</i>	A list of availability zones for the auto scaling group.	No
--default-cooldown <i>value</i>	The amount of time, in seconds, after a scaling activity completes before any further trigger-related scaling activities can start.	Yes
--desired-capacity <i>value</i>	The number of instances that should be running in the auto scaling group.	No
--grace-period <i>value</i>	Length of time in seconds after a new Amazon EC2 instance comes into service that Auto Scaling starts checking its health.	No
--health-check-type <i>value</i>	The type of health check: instance or load balancer.	No
--tags --value " <i>key1=value1,key2=value2...</i> "	A comma-delimited list of tags for this auto scaling group.	No
--termination-policies --value <i>value1,value2,value3...</i>	A delimited list of termination policies for this auto scaling group.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .

Option	Description
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

CloudWatch-Compatible Commands

Commands that begin with the `euwatch-` prefix are compatible with Amazon CloudWatch.

euwatch-delete-alarms

Deletes the alarm(s) with the specified name(s).

Syntax

```
euwatch-delete-alarms [AlarmNames [AlarmNames ...] ]
```

Options

Option	Description	Required
AlarmNames	Names of the alarms to delete. You can also set this value using <code>--alarm-name</code> .	No
<code>-f</code> , <code>--force</code>	Forces the delete to go through without prompting. By default, the delete command will prompt.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U</code> , <code>--url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I</code> , <code>--access-key-id value</code>	User's access key ID
<code>-S</code> , <code>--secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h</code> , <code>--help</code>	Display the manual page for the command.

Output

Eucalyptus does not return any output.

Example

The following example deletes the alarm named, `test-alarm`.

```
euwatch-delete-alarms --alarm-name test-alarm
```

euwatch-describe-alarm-history

Provides summary information or detailed history about the specified alarm.

Syntax

```
euwatch-describe-alarm-history [AlarmName] [--start-date value ]
[--end-date value ] [--history-item-type value ]
```

Options

Option	Description	Required
AlarmName	Names of the alarm. By default Eucalyptus returns history for all alarms. You can also set this value using <code>--alarm-name</code> .	No
<code>--start-date value</code>	Start of date range for history. By default it extends to all available history.	No
<code>--end-date value</code>	End of date range for history. Default: current time	No
<code>--history-item-type value</code>	Type of history items you want Eucalyptus to return. By default, Eucalyptus returns all types. Value values: : ConfigurationUpdate StateUpdate Action.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>EC2_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_CLOUDWATCH_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Eucalyptus returns a table with the following information:

- **ALARM:** Alarm name.
- **TIMESTAMP:** Timestamp.
- **TYPE:** Type of event, one of ConfigurationUpdate, StateUpdate and Action.
- **SUMMARY:** Human readable summary of history event.
- **DATA** Detailed data on event in machine readable JSON format. This column appears only in the `--show-long` view.

Examples

The following example requests all history items for the alarm, `my-alarm`.

```
euwatch-describe-alarm-history --alarm-name my-alarm --headers
```

The following is example output.

ALARM	TIMESTAMP	TYPE	SUMMARY
my-alarm	2010-05-07T18:46:16.121Z	Action	Published a notification to arn:aws:sns:...
my-alarm	2010-05-07T18:46:16.118Z	StateUpdate	Alarm updated from INSUFFICIENT_DATA to OK
my-alarm	2010-05-07T18:46:07.362Z	ConfigurationUpdate	Alarm "my-alm" created

euwatch-describe-alarms

Returns information about the specified alarm(s).

Syntax

```
euwatch-describe-alarms [AlarmNames [AlarmNames ...] ] [--action-prefix value]
[--alarm-name-prefix value] [--state-value value]
```

Options

Option	Description	Required
AlarmNames	Names of the alarms. You can also set this value using <code>--alarm-name</code> .	No
<code>--action-prefix value</code>	Prefix of action names.	No
<code>--alarm-name-prefix value</code>	Prefix of alarm names.	No
<code>--state-value value</code>	State of Alarm. Valid values: OK ALARM INSUFFICIENT_DATA	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Option	Description
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>EC2_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_CLOUDWATCH_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns a table that contains the following information:

- **ALARM:** Alarm name.
- **DESCRIPTION:** Alarm description. This column appears only in the `--show-long` view.
- **STATE:** Alarm state.
- **STATE_REASON:** Human readable reason for state. This column appears only in the `--show-long` view.
- **STATE_REASON_DATA:** Machine readable reason for state (JSON format). This column appears only in the `--show-long` view.
- **ENABLED:** Actions enabled or not. This column appears only in the `--show-long` view.
- **OK_ACTIONS:** Action to execute on OK status. This column appears only in the `--show-long` view.
- **ALARM_ACTIONS:** Action to execute on ALARM status.
- **INSUFFICIENT_DATA_ACTIONS:** Action to execute on INSUFFICIENT_DATA status. This column appears only in the `--show-long` view.
- **NAMESPACE:** Namespace for metric.
- **METRIC_NAME:** Metric name.
- **DIMENSIONS:** Dimensions. This column appears only in the `--show-long` view.
- **PERIOD:** Period.
- **STATISTIC:** Statistic.
- **UNIT:** Unit. This column appears only in the `--show-long` view.
- **EVAL_PERIODS:** Number of periods for which metric will be evaluated.
- **COMPARISON:** Comparison operator.
- **THRESHOLD:** Threshold.

Examples

The following example describes all of your alarms whose name starts with `my-alm`.

```
euwatch-describe-alarms --alarm-name-prefix my-alm --headers
```

The following is an example of output for this command.

```
ALARM STATE ALARM_ACTIONS NAMESPACE METRIC_NAME PERIOD STATISTIC
EVAL_PERIODS COMPARISON THRESHOLD
my-alm1 OK arn:aws:autoscaling:... AWS/EC2 CPUUtilization 60 Average
3 GreaterThanThreshold 100.0
```

```
my-alm2 OK arn:aws:autoscaling:.. AWS/EC2 CPUUtilization 60 Average
5 GreaterThanThreshold 80.0
```

euwatch-describe-alarms-for-metric

Provides information about alarms associated with a specified metric.

Syntax

```
euwatch-describe-alarms-for-metric --metric-name value --namespace value
[--dimensions "key1=value1,key2=value2..." ]
[--period value ] [--statistic value ] [--unit value ]
```

Options

Option	Description	Required
--dimensions "key1=value1,key2=value2..."	Dimensions of the metric on which to alarm.	No
--metric-name <i>value</i>	The name of the metric on which to alarm.	Yes
--namespace <i>value</i>	Namespace of the metric on which to alarm.	Yes
--period <i>value</i>	Period of metric on which to alarm.	No
--statistic <i>value</i>	The statistic of the metric on which to alarm. Valid values: SampleCount Average Sum Minimum Maximum	No
--unit <i>value</i>	The unit of the metric on which to alarm.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <i>EC2_REGION</i> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <i>AWS_CLOUDWATCH_URL</i> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

This command returns a table that contains the following information:

- **ALARM:** Alarm name.
- **DESCRIPTION:** Alarm description. This column appears only in the `--show-long` view.
- **STATE:** Alarm state.
- **STATE_REASON:** Human readable reason for state. This column appears only in the `--show-long` view.
- **STATE_REASON_DATA:** Machine readable reason for state (JSON format). This column appears only in the `--show-long` view.
- **ENABLED:** Actions enabled or not. This column appears only in the `--show-long` view.
- **OK_ACTIONS:** Action to execute on OK status. This column appears only in the `--show-long` view.
- **ALARM_ACTIONS:** Action to execute on ALARM status.
- **INSUFFICIENT_DATA_ACTIONS:** Action to execute on INSUFFICIENT_DATA status. This column appears only in the `--show-long` view.
- **NAMESPACE:** Namespace for metric.
- **METRIC_NAME:** Metric name.
- **DIMENSIONS:** Dimensions. This column appears only in the `--show-long` view.
- **PERIOD:** Period.
- **STATISTIC:** Statistic.
- **UNIT:** Unit. This column appears only in the `--show-long` view.
- **EVAL_PERIODS:** Number of periods for which metric will be evaluated.
- **COMPARISON:** Comparison operator.
- **THRESHOLD:** Threshold.

Example

The following example describes an alarm for the metric, CPUUtilization, for

```
euwatch-describe-alarms-for-metric --metric-name CPUUtilization --namespace
AWS/EC2 --dimensions InstanceId=i-abcdef
```

The following is example output for the command.

ALARM	STATE	ALARM_ACTIONS	NAMESPACE	METRIC_NAME	PERIOD	STATISTIC	EVAL_PERIODS	COMPARISON	THRESHOLD
my-alm1	OK	arn:aws:autoscaling:...	AWS/EC2	CPUUtilization	60	Average	3	GreaterThanThreshold	100.0
my-alm2	OK	arn:aws:autoscaling:...	AWS/EC2	CPUUtilization	60	Average	5	GreaterThanThreshold	80.0

euwatch-disable-alarm-actions

Disable all actions for an alarm.

Syntax

```
euwatch-disable-alarm-actions [AlarmNames [AlarmNames ...] ]
```

Options

Option	Description	Required
AlarmNames	List of alarm names you want to disable actions for	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Eucalyptus does not return any output.

Example

The following example disables all actions for `test-alarm`.

```
euwatch-disable-alarm-actions test-alarm
```

euwatch-enable-alarm-actions

Enables all actions for an alarm.

Syntax

```
euwatch-enable-alarm-actions [ALARM [ALARM ...] ]
```

Options

Option	Description	Required
ALARM	List of alarm names you want to enable all actions for	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .

Option	Description
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

Eucalyptus does not return any output.

Example

The following example enables all actions `test-alarm`.

```
euwatch-enable-alarm-actions --alarm-name test-alarm
```

euwatch-get-stats

Gets time-series data for one or more statistics for a given metric.

Syntax

```
euwatch-get-stats MetricName --namespace value
--statistics value[,value...] [--dimensions "key1=value1,
key2=value2..." ] [--end-time value ] [--period value ]
[--start-time value ] [--unit value ]
```

Options

Option	Description	Required
MetricName	Metric name that corresponds to the one contained in the gathered metric. You can also set this value using <code>--metric-name</code> .	Yes
--dimensions "key1=value1,key2=value2"	Dimensions (one or more) along which the metric data was originally stored. If no dimensions are specified, then the statistics belonging to the specified non-dimensional metric will be returned. If you don't enter a value for dimensions, Eucalyptus assumes there are no dimensions.	No
--end-time <i>value</i>	Timestamp of the last data point to return, inclusive. For example, 2009-11-25T19:00:00+00:00. Timestamp will be rounded down to the nearest minute. The <code>dateTime</code> type uses ISO 8601. Default: now	No

Option	Description	Required
<code>-n, --namespace value</code>	Namespace of the desired metric. This must match the namespace that was specified when the desired metric was initially reported.	Yes
<code>--period value</code>	Granularity, in seconds, of the returned data points. Period must be at least 60 seconds and must be a multiple of 60. Default: 60 seconds.	No
<code>-s, --statistics value1,value2,value3</code>	Statistics to be returned for the desired metric. Valid values: Average Sum Maximum Minimum	Yes
<code>--start-time value</code>	Timestamp of the first data point to return, inclusive. For example, 2009-11-25T19:00:00+00:00. Timestamp will be rounded down to the nearest minute. The dateTime type uses ISO 8601. Default: one hour in the past	No
<code>--unit value</code>	Unit that the metric was reported in. Valid values: Seconds Bytes Bits Percent Count Bytes/Second Bits/Second Count/Second None	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

This command returns a table that contains the following:

- Time: Time the metrics were taken.
- SampleCount: The number of data points used to calculate this statistic
- Average: Average value
- Sum: Sum of values

- Minimum: Minimum observed value
- Maximum: Maximum observed value
- Unit: Unit of the metric

Examples

The follow example returns the average, minimum, and maximum CPU utilization for instance i-c07704a9, at one hour resolution.

```
euwatch-get-stats CPUUtilization --start-time 2013-02-14T23:00:00.000Z
--end-time 2013-03-14T23:00:00.000Z --period 3600 --statistics
"Average,Minimum,Maximum" --namespace "AWS/EC2" --dimensions "InstanceId=i-
c07704a9"
```

The following example returns CPU utilization across your fleet.

```
euwatch-get-stats CPUUtilization --start-time 2013-02-14T23:00:00.000Z --end-
time
2013-03-14T23:00:00.000Z --period 3600 --statistics "Average,Minimum,Maximum"
--namespace "AWS/EC2"
```

The following example returns the average, minimum, and maximum request count made to the dev stack of TestService for a particular user, at one hour resolution.

```
euwatch-get-stats RequestCount --start-time 2012-11-24T23:00:00.000Z --end-
time
2012-11-25T23:00:00.000Z --period 3600 --statistics "Average,Minimum,Maximum"
--namespace
"TestService" --dimensions "User=SomeUser,Stack=dev"
```

The following example shows RequestCount statistics across all of "TestService".

```
euwatch-get-stats RequestCount --start-time 2012-11-24T23:00:00.000Z --end-
time
2012-11-25T23:00:00.000Z --period 3600 --statistics
"Average,Minimum,Maximum,SampleCount"
--namespace "TestService"
```

The following shows sample output for this command.

Time	Samples	Average	Unit
2013-05-19 00:03:00	2.0	0.19	Percent
2013-05-19 00:04:00	2.0	0	Percent
2013-05-19 00:05:00	2.0	0	Percent
2013-05-19 00:06:00	2.0	0	Percent
2013-05-19 00:07:00	2.0	0	Percent
2013-05-19 00:08:00	2.0	0	Percent
2013-05-19 00:09:00	2.0	0	Percent
2013-05-19 00:10:00	2.0	0	Percent
2013-05-19 00:11:00	2.0	0	Percent
2013-05-19 00:12:00	2.0	0.195	Percent
2013-05-19 00:13:00	2.0	0.215	Percent

euwatch-list-metrics

Lists the metrics associated with your account. You can filter metrics by using any combination of `MetricName`, `Namespace`, or `Dimensions`. If a you do not specify a filter, Eucalyptus returns all possible matches for the attribute. Note that any metric not seen for two weeks will expire and be removed from from this list.

Syntax

```
euwatch-list-metrics [--dimensions "key1=value1,key2=value2..." ]
[--metric-name value ] [--namespace value ]
```

Options

Option	Description	Required
<code>-d, --dimensions "key1=value1,key2=value2"</code>	Dimensions (one or more) along which the metric names are to be filtered. If you do not specify a dimension, Eucalyptus returns metric names with all possible dimensions.	No
<code>-m, --metric-name value</code>	Metric name that you want data for. If you do not specify a metric, Eucalyptus returns all possible metric names.	No
<code>-n, --namespace value</code>	Namespace along which metrics will be filtered. If you do not specify, Eucalyptus returns metric names from all possible namespaces.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Eucalyptus returns a table that contains the following information:

- Metric Name: name of the metric attached to this metric.
- Namespace: namespace associated with this metric.
- Dimensions: list of the dimension names and values associated with this metric.

Examples

The following example returns a list of all your metrics.

```
euwatch-list-metrics
```

The following example returns a list of all your metrics for a specified metric name.

```
euwatch-list-metrics --metric-name RequestCount
```

The following example returns a list of all your metrics for a specified namespace.

```
euwatch-list-metrics --namespace MyService
```

The following example returns a list of all your metrics for specified dimension names and values.

```
euwatch-list-metrics --dimensions "User=TestUser,Stack=Test"
```

The following is an example of the output.

Metric Name	Namespace	Dimensions
CPUUtilization	AWS/EC2	{InstanceId=i-e7e48a8e}
CPUUtilization	AWS/EC2	{InstanceId=i-231d744a}
CPUUtilization	AWS/EC2	{InstanceId=i-22016e4b}
CPUUtilization	AWS/EC2	{InstanceId=i-b0345cd9}
CPUUtilization	AWS/EC2	{InstanceId=i-539dff3a}
CPUUtilization	AWS/EC2	{InstanceId=i-af3544c6}
CPUUtilization	AWS/EC2	{InstanceId=i-d4f29ebd}
CPUUtilization	AWS/EC2	{ImageId=ami-de4daab7}
...		

euwatch-put-data

Adds metric data points to a metric.

Syntax

```
euwatch-put-data -m METRIC -n NAMESPACE
                    (-v FLOAT | -s
Maximum=FLOAT,Minimum=FLOAT,SampleCount=F
LOAT,Sum=FLOAT)
                    [-d key1=value1,key2=value2,...]
                    [-t YYYY-MM-DDThh:mm:ssZ] [-u UNIT]
                    [--show-empty-fields] [-U URL] [--region USER@REGION]
                    [-I KEY_ID] [-S KEY] [--security-token TOKEN]
                    [--debug] [--debugger] [--version] [-h]
```

Options

Option	Description	Required
-m METRIC, --metric-name METRIC	Name of the metric to which data points are to be added.	Yes
-n NAMESPACE, --namespace NAMESPACE, <i>value</i>	Namespace for the metric.	Yes
-v FLOAT, --value FLOAT, <i>value</i>	Data value for the metric. Exactly one of -v and -s is required.	Yes
-d, --dimensions "key1=value1,key2=value2..."	The dimensions of the metric to which data points are to be added.	No
-s, --statistic-values "key1=value1,key2=value2..."	Statistics to be provided for the given metric. You must specify all four of the key values you want for this option, or else Eucalyptus returns an error. Valid key values: SampleCount Sum Maximum Minimum	Yes
-t, --timestamp <i>value1,value2,value3...</i>	Timestamp of the data point. For example, 2009-11-25T19:00:00+00:00. Timestamp will be rounded down to the nearest minute. The dateTime type uses ISO 8601. The default for this option is the time that this request was sent.	No

Option	Description	Required
<code>-u, --unit value1,value2,value3...</code>	The unit that the metric is being reported in. Valid unit values are Seconds Bytes Bits Percent Count Bytes/Second Bits/Second Count/Second None	No
<code>-v, --value value1,value2,value3...</code>	The value of the metric datum being put in.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Eucalyptus does not return any output.

Examples

The following example puts statistic data for "RequestCount" in the "MyService" namespace. The metric contains no dimensions and so represents the overall RequestCount across the entire service. The measurement is a pre-aggregated statistic-values representing five earlier measurements whose maximum was 70, minimum was 30 and sum was 250.

```
euwatch-put-data --metric-name RequestCount --namespace "MyService"
--timestamp 2009-11-25T00:00:00.000Z --statistic-values
"Sum=250,Minimum=30,Maximum=70,SampleCount=5"
```

The following example puts user-specific "RequestCount" test data in the "MyService" namespace. The user and stack name are stored as dimensions in order to distinguish this metric from the service-wide metric in the example above.

```
euwatch-put-data --metric-name RequestCount --namespace "MyService"
--dimensions "User=testUser,Stack=Test" --timestamp 2009-11-25T00:00:00.000Z
--value 50
```

euwatch-put-metric-alarm

Creates a new alarm, or updates an existing alarm.

Syntax

```
euwatch-put-metric-alarm Alarm --comparison-operator value --evaluation-
periods value
--metric-name value --namespace value --period value --statistic
value --threshold value [--actions-enabled value ] [--alarm-actions
value [, value... ] ] [--alarm-description value ] [--dimensions
"key1=value1,key2=value2..." ] [--ok-actions value [, value... ] ] [--unit
value ] [--insufficient-data-actions value [, value... ] ]
```

Options

Option	Description	Required
<i>Alarm</i>	Name of the alarm.	Yes
--actions-enabled <i>value</i>	This determines if you want actions be executed when this alarm changes state. Valid values: true false	No
--alarm-actions <i>value1,value2,value3...</i>	Describes what you want to do if the alarm changes state. The value is the Amazon resource name (ARN) of the resource you want to act on.	No
--alarm-description <i>value</i>	Description of the alarm.	No
--comparison-operator <i>value</i>	The operator with which the comparison with threshold will be made. Valid values: GreaterThanOrEqualToThreshold GreaterThanThreshold LessThanThreshold LessThanOrEqualToThreshold	Yes
--dimensions " <i>key1=value1,key2=value2...</i> "	Dimensions of the metric on which to alarm. "	No
--evaluation-periods <i>value</i>	Number of consecutive periods for which the value of the metric needs to be compared to threshold.	Yes
--metric-name <i>value</i>	The name of the metric on which to alarm.	Yes
--namespace <i>value</i>	Namespace of the metric on which to alarm.	Yes
--ok-actions <i>value1,value2,value3...</i>	Describes what you want to do if the alarm goes to state OK. The value is the Amazon resource name (ARN) of the resource you want to act on.	No
--period <i>value</i>	Period of metric on which to alarm.	Yes
--statistic <i>value</i>	The statistic of the metric on which to alarm. Valid values: SampleCount Average Sum Minimum Maximum	Yes
--threshold <i>value</i>	The threshold with which the metric value will be compared.	Yes
--unit <i>value</i>	The unit of the metric on which to alarm.	No

Option	Description	Required
<code>--insufficient-data-actions value1,value2,value3..</code>	Describes what you want to do if the alarm goes to state <code>INSUFFICIENT_DATA</code> . The value is the Amazon resource name (ARN) of the resource you want to act on.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Eucalyptus does not return a response.

Example

The following example creates an alarm, `test-alarm`, that add a message to a topic when the CPU utilization of an instance exceeds 90% for three consecutive one minute periods.

```
euwatch-put-metric-alarm test-alarm --alarm-description "some desc"
--metric-name CPUUtilization --namespace AWS/EC2 --statistic Average --
period 60 --threshold
90 --comparison-operator GreaterThanThreshold --dimensions
AutoScalingGroupName=dev01
--evaluation-periods 3 --unit Percent --alarm-actions
arn:aws:autoscaling::scalingPolicy:45e9ed16-9462-4905-b9d4-ff99fecc0d43
:autoScalingGroupName/dev01:policyName/cap01-add
```

euwatch-set-alarm-state

Short reference description.

Syntax

```
euwatch-set-alarm-state AlarmName --state-reason value
--state-value value [--state-reason-data value ]
```

Options

Option	Description	Required
AlarmName	Name of the alarm. You can also set this value using "--alarm-name".	Yes
--state-reason <i>value</i>	Human-readable reason why this alarm was set to this state. Constraints: Must be in JSON format	No
--state-reason-data <i>value</i>	Machine-readable reason why this alarm was set to this state.	Yes
--state-value <i>value</i>	State to be set. Valid values: ALARM OK INSUFFICIENT_DATA	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

Eucalyptus does not return any output.

Example

The following example sets the state of the test-alarm alarm to OK.

```
euwatch-set-alarm-state --alarm-name test-alarm --state OK
```

CloudFormation-Compatible Commands

Commands that begin with the `euform-` prefix are compatible with Amazon CloudFormation.

Note: For more information about Amazon CloudFormation, see the [Amazon CloudFormation documentation](#).

euform-cancel-update-stack

Cancels a currently running stack update.

Syntax

```
euform-cancel-update-stack stackname
```

Options

Option	Description	Required
<code>stackname</code>	Names of the stack to stop updating.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Eucalyptus does not return any output.

euform-create-stack

Creates a new stack.

Syntax

```
euform-create-stack stackname (--template-file filename | --template-url URL)
[-d]
[-n ARN[,...]] [-p key=value] [-t minutes][--tag key[=value]]
```

Options

Option	Description	Required
stackname	Names of the new stack.	Yes
--template-file <i>filename</i>	Name of the file containing the new stack's JSON template.	No
--template-url <i>URL</i>	URL pointing to the new stack's JSON template.	No
-d, --disable-rollback	Disable rollback on failure.	No
-n, --notification-arns <i>ARN [,...]</i>	SNS ARNs to publish stack actions to	No
-p, --parameter <i>key=value</i>	Key and value of the parameters to use with the new stack's template, separated by an "=" character	No
-t, --timeout <i>minutes</i>	Timeout for stack creation.	No
--tag <i>key[=value]</i>	Key and optional value of the tag to create, separated by an "=" character. If no value is given the tag's value is set to an empty string.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

Eucalyptus does not return any output.

euform-delete-stack

Deletes a stack.

Syntax

```
euform-delete-stack stackname
```

Options

Option	Description	Required
stackname	Names of the stack to delete.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

Eucalyptus does not return any output.

euform-describe-stack-events

Returns a list of events that occurred in a stack.

Syntax

```
euform-describe-stack-events stackname
```

Options

Option	Description	Required
stackname	Names of the stack.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

Returns a list of stack events.

euform-describe-stack-resource

Returns information about a resource from the specified stack.

Syntax

```
euform-describe-stack-resource stackname -l resource
```

Options

Option	Description	Required
stackname	Names of the stack.	Yes
-l, --logical-resource <i>resource</i>	Logical ID of the resource to describe.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

euform-describe-stack-resources

Returns information about a resource from one or more stacks.

Syntax

```
euform-describe-stack-resource stackname -l resourceid -l resourceid
```

Options

Option	Description	Required
<code>stackname</code>	Limit the results to the specified stack.	Yes
<code>-l, --logical-resource resourceid</code>	Logical ID of the resource to describe.	Yes
<code>-p, --physical-resource resourceid</code>	Physical ID of the resource to describe.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Option	Description
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

euform-describe-stacks

Returns a list of events that occurred in a stack.

Syntax

```
euform-describe-stacks stackname
```

Options

Option	Description	Required
stackname	Names of the stack to describe.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.

Option	Description
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

Output

Returns a list of stacks.

euform-get-template

Returns a list of events that occurred in a stack.

Syntax

```
euform-get-template stackname
```

Options

Option	Description	Required
stackname	Names or ID of the active stack.	Yes

Common Options

Option	Description
- -show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
- -region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, - -url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, - -access-key-id <i>value</i>	User's access key ID
-S, - -secret-key <i>value</i>	User's AWS secret Key to use.
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

Output

Returns the stack template.

euform-list-stack-resources

Lists information about all of the resources in one or more stacks.

Syntax

```
euform-list-stack-resources stackname
```

Options

Option	Description	Required
stackname	Name of the stack to list resources from	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

euform-list-stacks

List all running stacks.

Syntax

```
euform-list-stacks stackname
```

Options

This command has no specific parameters.

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Returns a list of stacks.

euform-update-stack

Creates a new stack.

Syntax

```
euform-update-stack stackname (--template-file filename | --template-url URL)
[-p key=value]
```

Options

Option	Description	Required
<code>stackname</code>	Names of the stack to update.	Yes
<code>--template-file filename</code>	Name of the file containing the stack's updated JSON template.	No
<code>--template-url URL</code>	URL pointing to the stack's updated JSON template.	No
<code>-p, --parameter key=value</code>	Key and value of the parameters to use with the new stack's template, separated by an "=" character	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Option	Description
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Output

Eucalyptus does not return any output.

euform-validate-template

Validates a template.

Syntax

```
euform-validate-template (--template-file filename | --template-url URL)
[-p key=value]
```

Options

Option	Description	Required
<code>--template-file filename</code>	Name of the file containing the JSON template to validate.	No
<code>--template-url URL</code>	S3 URL pointing to the JSON template to validate.	No
<code>-p, --parameter key=value</code>	Key and value of the parameters to use with the new stack's template, separated by an "=" character	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .

Option	Description
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Output

Virtual Private Cloud (VPC)-Compatible Commands

This section covers commands that are compatible with Amazon Virtual Private Cloud (VPC).

Note: For more information about Amazon Virtual Private Cloud, see the [Amazon VPC documentation](#).

euca-accept-vpc-peering-connection

Accept a VPC peering connection request.

Syntax

```
euca-accept-vpc-peering-connection peer_connection_ID
```

Options

Option	Description	Required
<i>peer_connection_ID</i>	Identifier of the VPC peering connection to accept.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euca-assign-private-ip-addresses

Assign one or more private IP addresses to a network interface. Note that an instance's type may affect the number of addresses it can hold at once.

Syntax

```
euca-assign-private-ip-addresses -n INTERFACE
(--secondary-address ADDRESS | --secondary-count COUNT)
[--allow-reassignment]
```

Options

Option	Description	Required
<code>-n, --network-interface interface</code>	ID of the network interface to assign addresses.	Yes
<code>--secondary-address address, --secondary-private-ip-address count</code>	Assign a secondary address to the network interface. This parameter can be specified multiple times to add additional addresses.	No
<code>--secondary-count count [, --secondary-address address...]</code>	Automatically assign a specific number of secondary private IP addresses to the network interface.	No
<code>--allow-reassignment count [, --secondary-address address...]</code>	Allow addresses to be assigned even if they are already associated with other network interfaces.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

euca-associate-dhcp-options

Associate a DHCP option set with a VPC.

Syntax

```
euca-associate-dhcp-options -c vpc_id dhcp_options
```

Options

Option	Description	Required
-c, --vpc <i>VPC</i>	Identifier of the VPC to associate the DHCP option set with.	Yes
DHCHOPTS	Identifier of the DHCP option set to associate, or "default".	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

euca-attach-internet-gateway

Attach an Internet gateway to a VPC.

Syntax

```
euca-attach-internet-gateway -c vpc_id internet_gateway
```

Options

Option	Description	Required
-c, --vpc <i>VPC</i>	Identifier of the VPC to attach the internet gateway to.	Yes
internet_gateway	Identifier of the internet gateway to attach.	Yes

euca-attach-network-interface

Attach a VPC network interface to an instance.

Syntax

```
euca-attach-network-interface -i instance_id -d device_index interface
```

Options

Option	Description	Required
-i, --instance <i>instance_id</i>	Identifier of the instance to attach the network interface to.	Yes
-d, --device_index <i>device_index</i>	device index to attach the network interface with.	Yes
interface	network interface to attach to the instance.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euca-attach-vpn-gateway

Attach a virtual private gateway to a VPC.

Syntax

```
euca-attach-vpn-gateway -c vpc_id virtual_gateway
```

Options

Option	Description	Required
-c, --vpc <i>VPC</i>	Identifier of the VPC to attach the internet gateway to.	Yes
<i>virtual_gateway</i>	Identifier of the internet gateway to attach.	Yes

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euca-create-customer-gateway

Create a VPN customer gateway. You must also create a virtual private gateway using the `euca-create-vpn-gateway` command.

Syntax

```
euca-create-customer-gateway -t ipsec.1 -i ADDRESS [-b ASN]
```

Options

Option	Description	Required
-t <i>ipsec.1</i> , --type <i>ipsec.1</i>	The type of VPN connection to use. Valid values: <code>ipsec.1</code>	Yes
-i <i>address</i> , --ip <i>address</i>	The new customer gateway's cloud-facing IP address.	Yes
-b <i>ASN</i> , --bgp-asn <i>ASN</i>	The BGP AS number for the gateway.	Yes, if supported

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields as "(nil)".
<code>--region user@region</code>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
<code>-U, --url url</code>	URL of the cloud service to connect to. For administrative commands, this should be <code><ip_address>:8773/services/Empyrean</code> .
<code>-I, --access-key-id key_id</code>	User's access key ID.
<code>-S, --secret-key secret_key</code>	User's secret key.
<code>--security-token token</code>	User's security token.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>-h, --help</code>	Display the manual page for the command.
<code>--version</code>	Display the version of this tool.

euca-create-dhcp-options

Creates a DHCP option set.

Syntax

```
euca-create-dhcp-options key=value, [value, ...] [key=value, [value, ...]]
```

Options

Option	Description	
<code>key=value, [value, ...] [key=value, [value, ...]]</code>	One or more key/value sets for a DHCP option. Keys can have multiple values. Valid key options are <code>domain-name-servers</code> , <code>domain-name</code> , <code>ntp-servers</code> , <code>netbios-name-servers</code> , and <code>netbios-node-type</code> . See <i>Valid Key Options</i> section below.	Yes

Valid Key Options

The following table lists valid key options for a DHCP option set:

Option	Description
<code>domain-name-servers</code>	A comma-delimited list of up to 4 domain name servers.
<code>domain-name</code>	A domain name.
<code>ntp-servers</code>	A comma-delimited list of up to 4 NTP servers.
<code>netbios-name-servers</code>	A comma-delimited list of up to 4 NetBIOS name servers.

Option	Description	
netbios-node-type	The NetBIOS node type. Valid values are 1,2,4, or 8. See RFC 2132 for more information.	

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euca-create-internet-gateway

TBD

Syntax

Options

Option	Description	Required
--TBD <i>tbd</i>	Description.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .

Option	Description
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euca-create-nat-gateway

Creates a new VPC NAT gateway.

Syntax

```
euca-create-nat-gateway [-s SUBNETID] [-a ALLOCATIONID]
  [--show-empty-fields] [-U URL] [--region USER@REGION] [-I KEY_ID]
  [-S KEY] [--security-token TOKEN] [--debug] [--debugger] [--version] [-h]
```

Options

Option	Description	Required
-s, --subnet-id <i>subnetid</i>	The subnet in which to create the NAT gateway.	No
-a, --allocation-id <i>allocationid</i>	The allocation ID of an Elastic IP address to associate with the NAT gateway.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.

Option	Description
- -debugger	Enable interactive debugger on error.
-h, - -help	Display the manual page for the command.
- -version	Display the version of this tool.

Output

If an output was requested, then Eucalyptus returns a message stating that the NAT gateway was successfully created.

Example

To create a NAT gateway on a newly created VPC subnet:

```
create-nat-gateway --subnet-id vpc-6017a79e --allocation-id eipalloc-077d6221
```

Note: A subnet with NAT gateway(s) should appear in the network broadcast even if there are no running instances in the subnet.

euca-create-network-interface

TBD

Syntax

Options

Option	Description	Required
- -TBD <i>tbd</i>	Description.	No

Common Options

Option	Description
- -show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
- -region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, - -url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, - -access-key-id <i>value</i>	User's access key ID
-S, - -secret-key <i>value</i>	User's AWS secret Key to use.
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-create-route

Adds a route to a VPC route table.

Syntax

```
euca-create-route -r CIDR_ID
(-g GATEWAY | -i INSTANCE | -n NETWORKINTERFACEID | -p PEERCON)
[--show-empty-fields] [-U URL] [--region USER@REGION]
[-I KEY_ID] [-S KEY] [--security-token TOKEN]
[--debug] [--debugger] [--version] [-h]
RTABLE
```

Options

Option	Description	Required
<i>route_table_ID</i>	ID of the route table to add the route to.	Yes
<i>-r</i> , <i>--cidr CIDR_ID</i>	CIDR address block the route affects.	Yes
<i>-g</i> , <i>--gateway-id gateway_ID</i>	ID of the Internet gateway to target.	No
<i>-i</i> , <i>--instance instance_ID</i>	ID of a NAT instance to target.	No
<i>-n</i> , <i>--network-interface network_interface_id</i>	ID of a network interface to target.	No
<i>-p</i> , <i>--vpc-peering-connection peer_connection_ID</i>	ID of a VPC peering connection to target.	No

Common Options

Option	Description
<i>--show-empty-fields</i>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<i>--region value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<i>-U</i> , <i>--url value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<i>-I</i> , <i>--access-key-id value</i>	User's access key ID
<i>-S</i> , <i>--secret-key value</i>	User's AWS secret Key to use.
<i>--debug</i>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<i>--debugger</i>	Enable interactive debugger on error.
<i>--version</i>	Display the version of this tool.
<i>-h</i> , <i>--help</i>	Display the manual page for the command.

Example

The following example creates a route in route table `rtb-458d3256` that directs all network traffic to Internet gateway `igw-e1d19725`:

```
euca-create-route rtb-458d3256 -r 0.0.0.0/0 -g igw-e1d19725
```

This command should produce output similar to the following:

```
ROUTE igw-e1d19725 0.0.0.0/0
```

euca-create-route-table

Creates a new VPC route table.

Syntax

```
euca-create-route-table [--show-empty-fields] [-U URL]
[--region USER@REGION] [-I KEY_ID] [-S KEY]
[--security-token TOKEN] [--debug] [--debugger]
[--version] [-h]
VPC_ID
```

Options

Option	Description	Required
<i>VPC_ID</i>	The ID of the VPC to create the route table in.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Example

The following example creates a new route table in a VPC with the identifier of `vpc-15892437`:

```
euca-create-route-table vpc-15892437
```

This command should produce output similar to the following:

```
ROUTETABLE rtb-0ca8cac1 vpc-15892437
ROUTE local active 10.0.0.0/16 CreateRouteTable
```

euca-create-subnet

Creates a new VPC subnet.

Syntax

```
euca-create-subnet -c VPCID [-i CIDR] [-z AVAILABILITYZONE]
[--show-empty-fields] [-U URL] [--region USER@REGION] [-I KEY_ID]
[-S KEY] [--security-token TOKEN] [--debug] [--debugger] [--version] [-h]
```

Options

Option	Description	Required
-c, --vpc <i>VPCID</i>	Specify the ID of the VPC in which to create the new subnet.	Yes
-i, --cidr <i>CIDR</i>	Specify the CIDR address block for the new subnet.	Yes
-z, --availability-zone <i>availabilityzone</i>	Specify the availability zone in which to create the new subnet.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields as "(nil)".
--region <i>user@region</i>	Region and/or user name to search when looking up config file data. Only valid for EC2 endpoints.
-U, --url <i>url</i>	URL of the cloud service to connect to. For administrative commands, this should be <ip_address>:8773/services/Empyrean.
-I, --access-key-id <i>key_id</i>	User's access key ID.
-S, --secret-key <i>secret_key</i>	User's secret key.
--security-token <i>token</i>	User's security token.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
-h, --help	Display the manual page for the command.
--version	Display the version of this tool.

Output

If an output was requested, then Eucalyptus returns information about the newly created subnet.

Example

To create a VPC subnet 1bcb52d0 in the CIDR address block of 172.31.1.0/24:

```
euca-create-subnet -c vpc-1bcb52d0 -i 172.31.1.0/24
SUBNET subnet-02cedfcf available vpc-1bcb52d0 172.31.1.0/24 251 PARTI00 false
false
```

euca-create-vpc

Creates a new VPC.

Syntax

```
euca-create-vpc [--tenancy {default,dedicated}] [--show-empty-fields]
[-U URL] [--region USER@REGION] [-I KEY_ID] [-S KEY]
[--security-token TOKEN] [--debug] [--debugger]
[--version] [-h]
CIDR_block
```

Options

Option	Description	Required
<code>--tenancy</code> <i>default</i> <i>dedicated</i>	The type of instance tenancy to use.	No
<i>CIDR_block</i>	The IP address range for the VPC to use, in CIDR notation.	Yes

Output

- Output type identifier ("VPC")
- VPC ID
- Status
- CIDR address range
- DHCP option set ID
- Indicates a default VPC

Example

The following example creates a new VPC with the CIDR range 10.0.0.0/16

```
euca-create-vpc 10.0.0.0/16
```

This command will return output similar to the following:

```
VPC vpc-2a0af901 available 10.0.0.0/16 dopt-68a46350 default
```

euca-create-vpc-peering-connection

Creates a peering connection between two VPCs.

Syntax

```
euca-create-vpc-peering-connection -c vpc_id -p VPC [-o account-id]
```

Options

Option	Description	Required
<code>--vpc, -c vpc_id</code>	ID of the peering connection to request a connection from.	Yes
<code>--peer-vpc, -p vpc_id</code>	ID of the peering connection to request a connection to.	Yes
<code>--peer-owner-id, --o account_id</code>	Account ID of the peer VPC's owner. Default is the current user's account.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Example

The following example creates a peering connection

```
euca-create-vpc-peering-connection --vpc vpc-72ad7f86 --peer-vpc vpc-aa87a81b
```

euca-create-vpn-connection-route

Creates a static route that sends traffic from a virtual private gateway to a customer gateway.

Syntax

```
euca-create-vpn-connection-route --vpn-connection VPNCONN --cidr CIDR
```

Options

Option	Description	Required
<code>--vpn-connection gateway_ID</code>	Identifier of the virtual private gateway.	Yes

Option	Description	Required
<code>--cidr</code> <code>cidr_address</code>	Address block to add the route to	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-create-vpn-connection

Creates a VPN connection between a virtual private gateway and a customer gateway.

Syntax

```
euca-create-vpn-connection -t ipsec.1 --customer-gateway CGATEWAY
--vpn-gateway VGATEWAY [--static-routes-only]
[--format FORMAT] [--stylesheet STYLESHEET]
```

Options

Option	Description	Required
<code>-t, --type ipsec.1</code>	The type of VPN connection to use. Currently, the only valid value is <code>ipsec.1</code> .	Yes
<code>--customer-gateway gateway_ID</code>	Identifier of the customer gateway to connect.	Yes
<code>--vpn-gateway gateway_ID</code>	Identifier of the virtual private gateway to connect.	Yes
<code>--static-routes-only</code>	Use only static routes instead of BGP.	No

Option	Description	Required
<code>--format <i>format</i></code>	Show connection information in the specified format. Valid values: <code>cisco-ios-isr</code> , <code>juniper-junos-j</code> , <code>juniper-screens-6.1</code> , <code>juniper-screens-6.2</code> , <code>generic</code> , <code>xml</code> , or <code>none</code> Default value: <code>xml</code>	No
<code>--stylesheet <i>stylesheet</i></code>	Format the connection information using an XSL stylesheet. If the value contains "{format}" it will be replaced with the format chosen by the <code>--format</code> option. If the value is an HTTP or HTTPS URL it will be downloaded as needed. Default: value of the <code>vpn-stylesheet</code> region option.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region <i>value</i></code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url <i>value</i></code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id <i>value</i></code>	User's access key ID
<code>-S, --secret-key <i>value</i></code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-create-vpn-gateway

Creates the VPC side of a VPN connection. You will also need to create a VPN customer gateway using the `euca-create-customer-gateway` command.

Syntax

```
euca-create-vpn-gateway -t ipsec.1
```

Options

Option	Description	Required
<code>-t, --type <i>ipsec.1</i></code>	The type of VPN connection to use. Currently, the only valid value is <code>ipsec.1</code> .	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-delete-customer-gateway

Deletes a customer gateway.

Syntax

```
euca-delete-customer-gateway gateway_ID
```

Options

Option	Description	Required
<code>gateway_ID</code>	ID of the customer gateway to delete.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.

Option	Description
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-delete-dhcp-options

Deletes a VPC DHCP option set.

Syntax

```
euca-delete-dhcp-options dhcp_options_ID
```

Options

Option	Description	Required
<i>dhcp_options_ID</i>	ID of the DHCP option set to delete.	No

Common Options

Option	Description
- -show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
- -region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, - -url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, - -access-key-id <i>value</i>	User's access key ID
-S, - -secret-key <i>value</i>	User's AWS secret Key to use.
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-delete-internet-gateway

Deletes an VPC Internet gateway.

Syntax

```
euca-delete-internet-gateway gateway_ID
```

Options

Option	Description	Required
<i>gateway_ID</i>	ID of the Internet gateway to delete.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euca-delete-network-interface

Deletes a VPC network interface.

Syntax

```
euca-delete-network-interface interface_ID
```

Options

Option	Description	Required
<i>interface_ID</i>	ID of the network interface to delete.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Option	Description
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-delete-vpc

Deletes a specified VPC.

Syntax

```
euca-delete-vpc VPC_ID
```

Options

Option	Description	Required
<code>VPC_ID</code>	Identifier of the VPC to delete.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.

Option	Description
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-delete-vpc-peering-connection

Deletes a VPC peering connection.

Syntax

```
euca-delete-vpc-peering-connection connection_ID
```

Options

Option	Description	Required
<i>connection_ID</i>	ID of the VPC peering connection to delete.	No

Common Options

Option	Description
- -show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
- -region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, - -url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, - -access-key-id <i>value</i>	User's access key ID
-S, - -secret-key <i>value</i>	User's AWS secret Key to use.
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-delete-vpn-connection-route

Deletes a static route from a virtual private gateway to a customer gateway.

Syntax

```
euca-delete-vpn-connection-route - -vpn-connection VPNCONN - -cidr CIDR
```

Options

Option	Description	Required
<code>--vpn-connection gateway_ID</code>	Identifier of the virtual private gateway.	Yes
<code>--cidr cidr_address</code>	Address block to delete the route for.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-delete-vpn-connection

Deletes a VPN connection.

Syntax

```
euca-delete-vpn-connection connection_ID
```

Options

Option	Description	Required
<code>connection_ID</code>	Identifier of the VPN connection to delete.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Option	Description
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-delete-vpn-gateway

Deletes a virtual private gateway.

Syntax

```
euca-delete-vpn-gateway gateway_ID
```

Options

Option	Description	Required
<code>gateway_ID</code>	Identifier of the VPN gateway to delete.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.

Option	Description
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-describe-account-attributes

Shows information about your account.

Syntax

```
euca-describe-account-attributes [attribute [attribute ...]]
```

Options

Option	Description	Required
<i>attribute</i> <i>[attribute ...]</i>	Limit results to the specified account attributes.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-describe-customer-gateways

Shows information about VPN customer gateways.

Syntax

```
euca-describe-customer-gateways [--show-empty-fields] [-U URL]
[--region USER@REGION] [-I KEY_ID] [-S KEY]
[--security-token TOKEN] [--filter NAME=VALUE]
[--debug] [--debugger] [--version] [-h]
```

```
[VPC [VPC ...]]
```

Options

Option	Description	Required
gateway_ID [gateway_ID ...]	Limit results to one or more supplied customer gateway IDs.	No
-F, --filter name=value	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain customer gateways. For example, you can use a filter to return only the customer gateway that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a customer gateway only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify customer gateways that have a specific tag. Eucalyptus responds with the information for a customer gateway only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-customer-gateways`:

Filter	Description
bgp-asn	BGP AS number in use
customer-gateway-id	customer gateway-id ID
ip-address	ID of the customer gateway's cloud-facing interface
state	The state of the customer gateway
tag-key	key of a tag assigned to the customer gateway
tag-value	value of a tag assigned to the customer gateway
tag:KEY	specific tag key/value combination
type	type of the customer gateway

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region value	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url value	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .

Option	Description
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Example

The following example describes all customer gateways for an account.

```
euca-describe-customer-gateways
```

This command will return output similar to the following:

```
CUSTOMERGATEWAY cgw-a16d0fff
ATTACHMENT vpc-aa87a81b available
CUSTOMERGATEWAY cgw-a5f11fff
ATTACHMENT vpc-72ad7f86 available
```

euca-describe-dhcp-options

Shows information about VPC DHCP option sets.

Syntax

```
euca-describe-dhcp-options [--show-empty-fields] [-U URL]
[--region USER@REGION] [-I KEY_ID] [-S KEY]
[--security-token TOKEN] [--filter NAME=VALUE]
[--debug] [--debugger] [--version] [-h]
[dhcp_option_id [dhcp_option_id ...]]
```

Options

Option	Description	Required
<code>dhcp_option_id</code> <code>[dhcp_option_id ...]</code>	Limit results to one or more supplied dhcp option set IDs.	No
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain DHCP option sets. For example, you can use a filter to return only the DHCP option set that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a DHCP option set only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify DHCP option sets that have a specific tag. Eucalyptus responds with the information for a DHCP option set only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-dhcp-options`:

Filter	Description
<code>dhcp-options-id</code>	DHCP option set ID
<code>tag-key</code>	key of a tag assigned to the DHCP option set
<code>tag-value</code>	value of a tag assigned to the DHCP option set
<code>tag:KEY</code>	specific tag key/value combination
<code>type</code>	type of the DHCP option set

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Example

The following example describes all DHCP option sets for an account.

```
euca-describe-dhcp-options
```

This command will return output similar to the following:

```
DHCPOPTIONS dopt-4db27ac1
OPTION domain-name-servers AmazonProvidedDNS
OPTION domain-name example.internal
```

euca-describe-internet-gateways

Describe one or more VPC Internet gateways.

Syntax

```
euca-describe-internet-gateways [--show-empty-fields] [-U URL]
[--region USER@REGION] [-I KEY_ID] [-S KEY]
[--security-token TOKEN] [--filter NAME=VALUE]
[--debug] [--debugger] [--version] [-h]
[gateway_id [gateway_id ...]]
```

Options

Option	Description	Required
<i>gateway_ID</i> [<i>gateway_ID</i> ...]	Limit results to one or more supplied Internet gateway IDs.	No
-F, --filter <i>name=value</i>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space (" <i>name=value example</i> "). On a Windows system, use quotation marks even without a space in the value (" <i>name=value</i> ").	No

Available Filters

You can add filters to your request so that the response includes information for only certain Internet gateways. For example, you can use a filter to return only the Internet gateway that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for an Internet gateway only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify Internet gateways that have a specific tag. Eucalyptus responds with the information for a Internet gateway only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-internet-gateways`:

Filter	Description
<code>attachment.state</code>	attachment state, if the Internet gateway is attached to a VPC
<code>attachment.vpc-id</code>	ID of the VPC the Internet gateway is attached to
<code>internet-gateway-id</code>	Internet gateway-id ID
<code>tag-key</code>	key of a tag assigned to the Internet gateway
<code>tag-value</code>	value of a tag assigned to the Internet gateway
<code>tag:KEY</code>	specific tag key/value combination

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Example

The following example describes all Internet gateways for an account.

```
euca-describe-internet-gateways
```

This command will return output similar to the following:

```
INTERNETGATEWAY igw-016d0212
ATTACHMENT vpc-aa87a81b available
INTERNETGATEWAY igw-35f11866
ATTACHMENT vpc-72ad7f86 available
```

euca-describe-network-interface-attribute

Show attributes of a VPC network interface.

Syntax

```
euca-describe-network-interface-attribute
  --group-set | -a)
                                (-d | --source-dest-check |
                                [--show-empty-fields]
                                [-U URL]
                                [--region USER@REGION]
                                [-I KEY_ID] [-S KEY]
                                [--security-token TOKEN]
                                [--debug] [--debugger]
                                [--version] [-h]
                                interface_id
```

Options

Option	Description	Required
<i>interface_id</i>	ID of the network interface.	Yes
-d, --description	Show the description of the network interface.	No
--source-dest-check	Show whether source/destination checking is enabled.	No
--group-set	Show the security groups the network interface belongs to.	No
-a, --attachment	Show info about the interface's attachment (if any).	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euca-describe-network-interfaces

Show information about VPC network interfaces.

Syntax

```
euca-describe-network-interfaces [--show-empty-fields] [-U URL]
[--region USER@REGION] [-I KEY_ID]
[-S KEY] [--security-token TOKEN]
[--filter NAME=VALUE] [--debug]
[--debugger] [--version] [-h]
[interface_ID [interface_ID ...]]
```

Options

Option	Description	Required
[<i>interface_ID</i> <i>interface_ID ...</i>]	Limit results to the specified network interfaces.	No

Option	Description	Required
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain DHCP option sets. For example, you can use a filter to return only the network interface that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a network interface only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify network interfaces that have a specific tag. Eucalyptus responds with the information for a network interface only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-network-interface`:

Filter	Description
<code>addresses.private-ip-addresses</code>	the interface's private IP addresses
<code>addresses.primary</code>	whether the private IP address is the network interface's primary IP address
<code>addresses.association-id</code>	association ID for the network interface's elastic IP address
<code>addresses.association-owner-id</code>	owner ID of the addresses associated with the network interface
<code>association.association-id</code>	association ID of the network interface's IP address
<code>association.allocation-id</code>	allocation ID of the network interface's elastic IP address
<code>association.ip-owner-id</code>	owner ID of the network interface's elastic IP address
<code>association.ip-owner-id</code>	owner ID of the network interface's elastic IP address
<code>association.public-ip</code>	network interface's elastic IP address
<code>association.public-dns-name</code>	network interface's public DNS name
<code>attachment.attachment-id</code>	ID of the network interface's attachment
<code>attachment.instance-id</code>	ID of the instance the network interface is attached to

Filter	Description
<code>attachment.instance-owner-id</code>	owner ID of the instance the network interface is attached to
<code>attachment.device-index</code>	device index to which the network interface is attached
<code>attachment.status</code>	attachment status (attaching, attached, detaching, detached)
<code>attachment.attach-time</code>	time the network interface was attached
<code>availability-zone</code>	availability zone in which the network interface resides
<code>description</code>	network interface's description
<code>group-id</code>	ID of a security group associated with the network interface
<code>group-name</code>	name of a security group associated with the network interface
<code>mac-address</code>	MAC (hardware) address
<code>network-interface-id</code>	ID of the network interface
<code>owner-id</code>	account ID of the network interface's owner
<code>private-ip-address</code>	the network interface's private address(es)
<code>private-dns-name</code>	the network interface's private DNS name
<code>requester-id</code>	ID of the entity that created the network interface
<code>requester-managed</code>	whether the network interface is being managed by one of the cloud's services
<code>source-dest-check</code>	whether the network interface's traffic is subject to source/destination address checking
<code>status</code>	the interface's status (available, in-use)
<code>subnet-id</code>	ID of the subnet in which the network interface resides
<code>vpc-id</code>	ID of the VPC in which the network interface resides
<code>tag-value</code>	value of a tag assigned to the DHCP option set
<code>tag:KEY</code>	specific tag key/value combination
<code>type</code>	type of the DHCP option set

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (<code>nil</code>) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID

Option	Description
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Example

The following example describes all network interfaces for an account.

```
euca-describe-network-interfaces
```

This command will return output similar to the following:

```
NETWORKINTERFACE eni-79a17793 subnet-b1ad288b vpc-72ad7f86 085276049315 in-use
10.0.0.176 true
ATTACHMENT 0 attached 2014-12-11T08:40:05.899Z true
PRIVATEIPADDRESS 10.0.0.176 primary
```

euca-describe-vpc-attribute

Show an attribute of a VPC.

Syntax

```
euca-describe-vpc-attribute (-d | -s) VPC_ID
```

Options

Option	Description	Required
<i>VPC_ID</i>	ID of the VPC.	No
-d, --dns-hostnames	Show whether instances in the VPC are assigned DNS hostnames. Cannot be specified if the -s option is specified.	No
-s, --dns-support	Show whether DNS resolution is enabled. Cannot be specified if the -d option is specified.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .

Option	Description
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-describe-vpcs

Describes available VPCs.

Syntax

```
euca-describe-vpcs [--show-empty-fields] [-U URL]
  [--region USER@REGION] [-I KEY_ID] [-S KEY]
  [--security-token TOKEN] [--filter NAME=VALUE]
  [--debug] [--debugger] [--version] [-h]
  [VPC [VPC ...]]
```

Options

Option	Description	Required
VPC_ID [VPC_ID ...]	Limit results to one or more supplied VPC IDs.	No
<code>-F, --filter name=value</code>	Filter for limiting the results. See the table in the Available Filters section for a list of filters. Use quotation marks if the value has a space ("name=value example"). On a Windows system, use quotation marks even without a space in the value ("name=value").	No

Available Filters

You can add filters to your request so that the response includes information for only certain VPCs. For example, you can use a filter to return only the VPC that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a VPC only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify VPCs that have a specific tag. Eucalyptus responds with the information for a VPC only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `*eucalyptus?\` searches for the literal string `*eucalyptus?\`.

The following are the available filters for `euca-describe-vpcs`:

Filter	Description
<code>cidr</code>	CIDR address block

Filter	Description
dhcp-options-id	DHCP option set ID
isDefault	The VPC is a default VPC
state	The state of the VPC
tag-key	key of a tag assigned to the VPC
tag-value	value of a tag assigned to the VPC
tag:KEY	specific tag key/value combination
vpc-id	the ID of the VPC

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Example

The following example describes all VPCs for an account.

```
euca-describe-vpcs
```

This command will return output similar to the following:

```
VPC vpc-2a0af901 available 10.0.0.0/16 dopt-68a46350 default
```

euca-describe-vpc-peering-connections

Show information about VPC peering connections.

Syntax

```
euca-describe-vpc-peering-connections [connection_ID [connection_ID ...]]
```

Options

Option	Description	Required
<code>[connection_ID [connection_ID ...]]</code>	limit results to specific VPC peering connections.	No

Available Filters

You can add filters to your request so that the response includes information for only certain VPCs. For example, you can use a filter to return only the VPC that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a VPC only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify VPCs that have a specific tag. Eucalyptus responds with the information for a VPC only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus\?\` searches for the literal string `*eucalyptus?.`

The following are the available filters for `euca-describe-vpcs`:

Filter	Description
<code>accepter-vpc-info.cidr-block</code>	the peer VPC's CIDR address block
<code>accepter-vpc-info.owner-id</code>	the peer VPC's owner's account ID
<code>accepter-vpc-info.vpc-id</code>	the peer VPC's ID
<code>expiration-time</code>	when the peering connection request expires
<code>requester-vpc-info.cidr-block</code>	the requester VPC's CIDR address block
<code>requester-vpc-info.owner-id</code>	the requester VPC's owner's account ID
<code>requester-vpc-info.vpc-id</code>	the requester VPC's ID
<code>status-code</code>	the peering connection's status (active, deleted, expired, failed, pending-acceptance, provisioning, rejected)
<code>tag-key</code>	key of a tag assigned to the VPC
<code>tag-value</code>	value of a tag assigned to the VPC
<code>tag:KEY</code>	specific tag key/value combination
<code>vpc-peering-connection-id</code>	the peering connection's ID

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Option	Description
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-describe-vpn-connections

Show information about VPN connections.

Syntax

```
euca-describe-vpn-connections [--format format]
[--stylesheet stylesheet] [vpn_connection_ID [vpn_connection_ID ...]]
```

Options

Option	Description	Required
<code>vpn_connection_ID</code> <code>[vpn_connection_ID ...]</code>	Description.	No
<code>--format format</code>	Show connection information in the specified format. Valid values: <code>cisco-ios-isr</code> , <code>juniper-junos-j</code> , <code>juniper-screenos-6.1</code> , <code>juniper-screenos-6.2</code> , <code>generic</code> , <code>xml</code> , or <code>none</code> Default value: <code>xml</code>	No
<code>--stylesheet stylesheet</code>	Format the connection information using an XSL stylesheet. If the value contains "{format}" it will be replaced with the format chosen by the <code>--format</code> option. If the value is an HTTP or HTTPS URL it will be downloaded as needed. Default: value of the <code>vpn-stylesheet</code> region option.	No

Available Filters

You can add filters to your request so that the response includes information for only certain VPC connections. For example, you can use a filter to return only the VPC connection that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a VPC connection only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify VPC connections that have a specific tag. Eucalyptus responds with the information for a VPC connection only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.
- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-vpc-connections`:

Filter	Description
<code>bgp-asn</code>	the BGP AS number advertised by the customer gateway router
<code>customer-gateway-configuration</code>	connection information for the customer gateway
<code>customer-gateway-id</code>	ID of the connected customer gateway
<code>state</code>	the VPN connection's state (available, deleting, deleted, pending)
<code>option.static-routes-only</code>	whether the VPN connection is restricted to static routes instead of using BGP
<code>route.destination-cidr-block</code>	the address block corresponding to the subnet used in the data center behind the customer gateway router
<code>tag-key</code>	key of a tag assigned to the VPC
<code>tag-value</code>	value of a tag assigned to the VPC
<code>tag:KEY</code>	specific tag key/value combination
<code>vpc-connection-id</code>	the VPN connection's ID
<code>vpc-gateway-id</code>	ID of the connected virtual private gateway

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.

Option	Description
-h, --help	Display the manual page for the command.

euca-describe-vpn-gateways

Show information about virtual private gateways.

Syntax

```
euca-describe-vpn-gateways [vgateway_ID [vgateway_ID ...]]
```

Options

Option	Description	Required
<i>vgateway_ID</i>	Limit results to specific virtual private gateways.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

Available Filters

You can add filters to your request so that the response includes information for only certain VPC gateways. For example, you can use a filter to return only the VPC gateway that has a specific ID. Some tips for using filters with this command:

- You can use multiple values for a filter. Eucalyptus responds with information for a VPC gateway only if it matches at least one of the filter values that you specified.
- You can use multiple filters. For example, you can specify VPC gateways that have a specific tag. Eucalyptus responds with the information for a VPC gateway only if it matches all the filters that you specified. If there is no match, Eucalyptus returns an empty response.

- You can use wildcards in a filter value. Use an asterisk (*) to match zero or more characters. Use a question mark (?) to match exactly one character. To escape special characters, use a backslash (\) before the character. For example, a value of `\*eucalyptus?\` searches for the literal string `*eucalyptus?`.

The following are the available filters for `euca-describe-vpc-gateways`:

Filter	Description
<code>attachment.state</code>	state of attachment with a VPC
<code>attachment.vpc-id</code>	ID of a VPC the virtual private gateway is attached to
<code>availability-zone</code>	availability zone in which the virtual private gateway resides
<code>tag-key</code>	key of a tag assigned to the VPC
<code>tag-value</code>	value of a tag assigned to the VPC
<code>tag:KEY</code>	specific tag key/value combination
<code>vpc-connection-id</code>	the VPN connection's ID
<code>vpc-gateway-id</code>	ID of the virtual private gateway

euca-detach-internet-gateway

Detach an Internet gateway from a VPC. The VPC must not contain running instances with elastic IP addresses.

Syntax

```
euca-detach-internet-gateway -c VPC_ID gateway_ID
```

Options

Option	Description	Required
<code>gateway_ID</code>	ID of the Internet gateway to detach.	Yes
<code>-c, --vpc VPC_ID</code>	ID of the VPC to detach from.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.

Option	Description
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-detach-network-interface

Detach a VPC network interface from an instance.

Syntax

```
euca-detach-network-interface [-f] attachment_ID
```

Options

Option	Description	Required
<i>attachment_ID</i>	ID of the network interface attachment.	Yes
-f, - -force	Force the network interface to detach immediately.	No

Common Options

Option	Description
- -show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
- -region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, - -url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, - -access-key-id <i>value</i>	User's access key ID
-S, - -secret-key <i>value</i>	User's AWS secret Key to use.
- -debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-detach-vpn-gateway

Detach a virtual private gateway from a VPC.

Syntax

```
euca-detach-vpn-gateway -c VPC_ID gateway_ID
```

Options

Option	Description	Required
<i>gateway_ID</i>	ID of the VPN gateway.	Yes
<i>-c, --vpc VPC_ID</i>	VPC to detach the virtual private gateway from.	Yes

Common Options

Option	Description
<i>--show-empty-fields</i>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<i>--region value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<i>-U, --url value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<i>-I, --access-key-id value</i>	User's access key ID
<i>-S, --secret-key value</i>	User's AWS secret Key to use.
<i>--debug</i>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<i>--debugger</i>	Enable interactive debugger on error.
<i>--version</i>	Display the version of this tool.
<i>-h, --help</i>	Display the manual page for the command.

euca-disable-vgw-route-propagation

Make a VPC route table stop obtaining routes from a virtual private gateway.

Syntax

```
euca-disable-vgw-route-propagation --route-table rtable_id --vgw gateway_id
```

Options

Option	Description	Required
<i>--route-table rtable_id</i>	Identifier of the route table to stop propagating routes to.	Yes
<i>--vgw gateway_id</i>	Identifier of the route table to stop propagating routes to.	Yes

Common Options

Option	Description
<i>--show-empty-fields</i>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.

Option	Description
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-enable-vgw-route-propagation

Allow a VPC route table to obtain routes from a virtual private gateway.

Syntax

```
euca-enable-vgw-route-propagation --route-table rtable_id --vgw gateway_id
```

Options

Option	Description	Required
<code>--route-table <i>rtable_id</i></code>	Identifier of the route table to propagate routes to.	Yes
<code>--vgw <i>gateway_id</i></code>	Identifier of the route table to propagate routes to.	Yes

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using <code>(nil)</code> as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.

Option	Description
- -debugger	Enable interactive debugger on error.
- -version	Display the version of this tool.
-h, - -help	Display the manual page for the command.

euca-modify-network-interface-attribute

Modify an attribute of a VPC network interface.

Syntax

```
euca-modify-network-interface-attribute
(-d description | --source-dest-check (true|false) | --group-id group_id
| -a attachment)
[--delete-on-termination (true|false)]
interface_id
```

Options

Option	Description	Required
-d, --description <i>description</i>	Set the interface's description.	No
--source-dest-check <i>boolean</i>	Set whether source/destination checking is enabled. Valid values: true or false	No
--group-id <i>group</i> [<i>group...</i>]	Set the security group(s) that the interface belongs to.	No
-a, --attachment <i>attachment</i>	ID of an attachment to modify. You must specify the --delete-on-termination option when this option is used.	No
--delete-on-termination <i>boolean</i>	Set whether the interface's attachment will be deleted when the instance terminates. You must specify the --attachment option when this option is used. Valid values: true or false	No
<i>interface_id</i>	Identifier of the network interface.	Yes

Common Options

Option	Description
- -show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
- -region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID

Option	Description
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-modify-vpc-attribute

Modify an attribute of a VPC.

Syntax

```
euca-modify-vpc-attribute [-c VPC] (-d (true|false) | -s (true|false))
```

Options

Option	Description	Required
<code>-c, --vpc vpc_id</code>	Identifier of the VPC to modify.	Yes
<code>-d, --dns-hostnames boolean</code>	Enable or disable assignment of DNS names to instances. Valid values: true or false	No
<code>-s, --dns-support boolean</code>	Enable or disable DNS resolution. Valid values: true or false	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.

Option	Description
-h, --help	Display the manual page for the command.

euca-reject-vpc-peering-connection

Reject a request for a VPC peering connection To delete an active VPC peering connection or a peering connection request you created, use `euca-delete-vpc-peering-connection`.

Syntax

```
euca-reject-vpc-peering-connection connection_id
```

Options

Option	Description	Required
<i>connection_id</i>	Description.	No

Common Options

Option	Description
--show-empty-fields	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
--region <i>value</i>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
-U, --url <i>value</i>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
-I, --access-key-id <i>value</i>	User's access key ID
-S, --secret-key <i>value</i>	User's AWS secret Key to use.
--debug	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
--debugger	Enable interactive debugger on error.
--version	Display the version of this tool.
-h, --help	Display the manual page for the command.

euca-reset-network-interface-attribute

Reset an attribute of a VPC network interface.

Syntax

```
euca-reset-network-interface-attribute --source-dest-check
interface_id
```

Options

Option	Description	Required
<code>--source-dest-check <i>boolean</i></code>	Enable source/destination checking. Valid values: true or false	No
<code><i>interface_id</i></code>	Description.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region <i>value</i></code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url <i>value</i></code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id <i>value</i></code>	User's access key ID
<code>-S, --secret-key <i>value</i></code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

euca-unassign-private-ip-addresses

TBD

Syntax

```
euca-unassign-private-ip-addresses -n interface_id
  -secondary-address address
```

Options

Option	Description	Required
<code>-n, --network-interface <i>interface_id</i></code>	Identifier of the network interface to remove addresses from.	No
<code>--secondary-address, --secondary-private-ip-address <i>address</i></code>	IP address to remove from the network interface. Use this option multiple times to remove additional addresses.	No

Common Options

Option	Description
<code>--show-empty-fields</code>	Show empty fields using (nil) as a placeholder to indicate that this data was not requested. Empty fields are not shown by default.
<code>--region value</code>	Specify region value as the cloud region to use. You can set this by using the environment variable <code>AWS_DEFAULT_REGION</code> .
<code>-U, --url value</code>	Overrides the URL for the service call with the value entered. You can set this by using the environment variable <code>AWS_AUTOSCALING_URL</code> .
<code>-I, --access-key-id value</code>	User's access key ID
<code>-S, --secret-key value</code>	User's AWS secret Key to use.
<code>--debug</code>	Prints what the command sends to the server and what it receives from the server. Use when you're trying to debug Euca2ools.
<code>--debugger</code>	Enable interactive debugger on error.
<code>--version</code>	Display the version of this tool.
<code>-h, --help</code>	Display the manual page for the command.

Euca2ools Guide History

This section contains information about changes to the Euca2ools documentation in this release.

Section / Topic	Description of Change	Date Changed
<u>Installing Euca2ools on RHEL / CentOS</u>	Removed RHEL 6 / 7 info, which applied only to 4.3.x releases.	March 2017
Euca2ools	Add new commands: euare-getcallerid.	March 2017